Qlik Gold Client<sup>™</sup>



# Configuration and Utilities User Guide 8.6

# Copyright

© 2012-2020 Qlik Analytics (ISR) Ltd. All rights reserved.

No part of this document may be reproduced or transmitted in any form or for any purpose without the express permission of Qlik Analytics (ISR) Ltd.

Qlik Analytics (ISR) Ltd. makes no warranties or representations with respect to the content hereof, and assumes no responsibility for errors in this document. Qlik Analytics (ISR) Ltd. shall not be liable for special, indirect, incidental, or consequential damages, including without limitation, lost revenues or lost profits which may result from the use of these materials. The information contained in this document is subject to change without notice.

# **Trademarks**

Gold Client and the Gold Client logo are registered trademarks of Qlik Analytics (ISR) Ltd., Inc.

SAP, SAP NetWeaver, ABAP and other SAP products and services mentioned herein as well as their respective logos are trademarks or registered trademarks of SAP AG in Germany and in several other countries all over the world.

All other product and company names herein may be trademarks of their respective owners.

# **Table of Contents**

#### Introduction

### Configuration

- Installation Setup
  - Installation Setup
  - Custom Table Discovery
  - Setup Confirmation
- Data Wave
- Framework
  - Client Construct
  - o Data Echo
  - Data Type Hierarchy Report
  - Tables Missing Field Relations
  - Set Data Snap Record Limits
  - Maintain Data Type Tags
  - S4 Exclude Fields
  - Config Download/Upload (JSON)
- Intelligent Slice
- Parallel Processing
- Global Scenario Variables
- Structure Differences
- Select Optimization
- Memory Optimization
- Transform Order
- Application Settings (mconfig)
- Configure Auto Import RFC
- Simulate Export Setup
- Maintain User Exits

### Utilities

- Logical System Configuration
- Logical System Mapping
- Activity Log
- Configuration Change Log
- Configuration Download

#### **Advance Utilities**

- Passport File Utility
- Activity Log Cleanup
- Stranded Files Cleanup
- Export ID Manager
- Scenario Manager
- Change Gold Client File Path
- Export Table Data (CC)
- Resend Subset Sync Job

#### System

- Cross-Client File Names/Paths
- Number Range Buffer
- Datatype Change Pointers

#### **New Utilities**

- Restart Failed Jobs
- Table Cleanup Utility
- Global Parameter Maintenance
- SQL Trace Comparison
- Memory optimization upgrade
- Compression Exception by Table
- Export progress report
- Maintain Timestamp types
- Export Dashboard
- Tablename Mapping

A select number of utilities have been moved out of the Configuration area and relocated to the main Gold Client screen under the function named **Post Process** (within the Data Echo area). All of these utilities have a common purpose and that is to perform conversion of client values that are stored as part of the data value.

#### Conversion

- Maintain Change Doc Userexit Config
- Update Change Document Client
- Utility to Update Client Value
- Update Person Where-Used Addr Client

#### Support Information

Figure 1.0

# Introduction

This user guide provides detailed insight into accessing and executing the various configuration functions and utilities available in Gold Client.

The Gold Client configuration and utilities are easily accessible from the main Gold Client page (transaction ZGOLD) by selecting the 'Configuration' button located in the lower right-hand corner. The result is that the Gold Client Setup Utility page is displayed (Fig 1.0). Within the Gold Client Setup Utility screen, the various functions are organized into six primary folders: Configuration, Utilities, Advance Utilities, System, New Utilities, and SCM. A select number of functions are further organized into sub-folders.

Gold Client Setup Utility					
<ul> <li>Configuration</li> <li>Utilities</li> <li>Advance Utilities</li> <li>System</li> <li>New Utilities</li> <li>SCM</li> </ul>					

Figures 1.1 - 1.6 show all the executables within each of the primary folders.

#### Figure 1.1

<ul> <li>Configuration</li> </ul>
🔹 🛅 Installation/Setup
• 🚱 Installation Setup
・ 🚱 Custom Table Discovery
• 🐼 Setup Confirmation
• 🐼 S4 Table Utility
🔻 🛅 Data Wave
• 🚱 Initialize Client Config
• 🐼 Source/Target Config
• 🚱 Post Processing Config
• 🐼 Set Default Variants
• 🐼 Data Discovery Variant Maint.
• 🐼 Set DataWave Relevance Flag
🝷 🛅 Framework
• 🐼 Client Construct
• 🐼 Data Echo
• 🐼 Data Type Hierarchy Report
• 🍄 Tables Missing Field Relations
• 🍄 Set Data Snap Record Limits
• 🚱 Maintain Data Type Tags
• 🐼 S4 Exclude Fields
• 🐼 Config Download/Upload (JSON)
• 🚱 Intelligent Slice
• 🚱 Parallel Processing
• 🚱 Global Scenario Variables
・ 🚱 Structure Differences
<ul> <li>Select Optimization</li> </ul>
・ 🐼 Memory Optimization
• 🐼 Transform Order
<ul> <li>Application Settings (mconfig)</li> </ul>
• 🚱 Configure Auto Import RFC
• 🊱 Simulate Export Setup
• 🚱 Maintain User Exits
• 🐼 Maintain Evaluation Path

<ul> <li>HR</li> <li>Logical System Configuration</li> <li>Logical System Mapping</li> <li>Activity Log</li> <li>Configuration Change Log</li> <li>Configuration Download</li> </ul>	🔹 🗁 Utilities	
<ul> <li>Logical System Configuration</li> <li>Logical System Mapping</li> <li>Activity Log</li> <li>Configuration Change Log</li> <li>Configuration Download</li> </ul>	• 🛅 HR	
<ul> <li>Interpretation of the second system Mapping</li> <li>Interpretation Change Log</li> <li>Interpretation Download</li> </ul>	• 🚱 Logical System Configuration	
<ul> <li>Activity Log</li> <li>Configuration Change Log</li> <li>Configuration Download</li> </ul>	• 🚱 Logical System Mapping	
<ul> <li>We configuration Change Log</li> <li>We configuration Download</li> </ul>	• 🚱 Activity Log	
<ul> <li>Configuration Download</li> </ul>	• 🚱 Configuration Change Log	
	• 🚱 Configuration Download	

Figure 1.2

	Figure 1.3
🕆 📂 Advance Utilities	
• 🐼 Passport File Utility	
・ 🐼 Activity Log Cleanup	
• 🐼 Stranded Files Cleanup	
• 🚱 Export ID Manager	
• 🚱 Scenario Manager	
• 🕼 Change Gold Client File Path	
• 🕼 Export Table Data (CC)	
• 🐼 Resend Subset Sync Job	
· · ·	
<b>.</b> ,	Figure 1.4
🕶 🛅 System	
• ি Cross-Client File Names/Paths	
• 🕸 Number Range Buffer	
<ul> <li>Datatype Change Pointers</li> </ul>	
	Figure 1.5
New Utilities	
• W Restart Failed Jobs	
W Table Cleanup Utility	
• 🦃 Global Parameter Maintenance	
• 🎡 SQL Trace Comparison	
• 🎡 Memory optimization upgrade	
<ul> <li>W Compression Exception by Table</li> </ul>	
• 🚱 Export progress report	
• 🚱 Maintain Timestamp types	
• 🚱 Export Dashboard	
• 🐼 Tablename Mapping	
	Eiguro 1 6
r 🖻 SCM	Figure 1.6
APO-CIE Configuration	-
Maintain table /HTG/GCS_ALTMAP	
Maintain table /HTG/GCS_ALTOR1	

# Configuration

### Installation Setup

This is an entry point into the Auto Config utility which is primarily intended for when Gold Client is being initially deployed; however, some programs may provide value beyond the initial deployment which is why they are segregated into two sections, one being for 1-time execution and the other being for periodic execution.

The suite of utilities included here consists of: Configure COPA, Deactivate Linkages, Removing Non-Existent Tables, Initialize /HTG/number ranges, Configure Master Data Tables, and Configure Custom Table. The programs can be executed individually or collectively as required, but from a practicality standpoint, most users would likely favor individual execution.

The content that follows describes each of these programs in greater detail (Fig. 2.0).

		Figure 2.0
Operating Concern		
	Operating Concern	Operating Concern

### **Configure COPA**

Since CO-PA (Profitability Analysis) tables are always unique for each customer it is necessary to create the data types within the Data Echo framework so that the data stored in these tables can be successfully copied. If you do not use CO-PA, then this utility is not relevant.

To run this utility, just check the 'Configure COPA' box, input the correct Operating Concern(s), and select 'Execute' (Fig. 2.1).

			Figure 2.1
✓ Configure COPA	Operating Concern	S001	<b>=</b>

The tables being updated by this utility all reside within the Gold Client namespace (/HTG/\*). Here is what the output looks like after having executed the Configure COPA utility (Fig. 2.2).

				Figure 2.2
START OF REPORT				
/HTG/GC_HEAD: CO	0 - PA	(CE1S_AL)		
/HTG/GC_HEAD: CO	0 - PA	(CE3S_AL)		
/HTG/GC_HEAD: CO	0 - PA	(CE4S_AL)		
/HTG/GC_HEAD: CO	0 - PA	(CE4S_AL_ACCT)		
/HTG/GC_TABLES1:	CO -	PA (CE1S_AL)	CE1S_AL	
/HTG/GC_TABLES1:	CO -	PA (CE3S_AL)	CE3S_AL	
/HTG/GC_TABLES1:	CO -	PA (CE4S_AL)	CE4S_AL	
/HTG/GC_TABLES1:	CO -	PA (CE4S_AL_ACCT)	CE4S_AL_ACCT	

Here is a sample result of executing this utility where the Data Echo data types have been created, including the associated tables and linkages (Fig. 2.3).

					Figure 2
G	old Client Data Frame	work			
E	Create 🖶 Copy 🚘 Delete	🖥 Master Data Type	🐨 Transaction Data Typ	e 🍞 Primary	Data Type 🛛 😽 D
Da	ta Framework	-	CO - PA (CE18	S_AL)	
	• 🛄 Tables	•	Datatype Kind F	File ID	Primary Prima
	• 🖋 Linkages		Transactional 0	CE1S_A	
	• 🌮 Connector • 🎼 Data Snap		3 2 7 H D	🔂 . 🔁 . 🤇	2
	• 🔲 Scenarios		Tables [ Display Mode ]		
	Export Memory Config		Table Name Source	Head Flg Sec.	Flag Data Eleme
		33	CE1S_AL CE1S_AL		
	▶ B CO - PA (CE4S_AL_ACCT)		-		

#### **Deactivate Linkages**

This utility will set Recipient Data Types which are not relevant to the customer's system as inactive. The benefit here is that it helps optimize the data export process. Alternatively, any Recipient Data Type links can be deactivated manually.

Let's take a hypothetical example that your system is not using the New GL functionality and thus there is no data to copy in those relevant tables. Executing this utility would then set the Recipient Data Type FI – GL ITEMS (FAGLFLEX) to be inactive (Fig. 2.4).

Gold Client Data Framework							
🛃 Create 🔹 Copy 🔂 Delete 🏾 🖗 Master Data Type	🔓 Trar	nsaction Data Type	Primary D	ata Type	😽 Disp	olay All	
Data Framework  Figure Figure Figure Provide Additional Structure Provided Additionae Structure		FI - FINANC		1ENTS			
<ul> <li>▶ I - FINANCE DOCS FROM REBATES</li> <li>▼ ☐ FI - FINANCE DOCUMENTS</li> </ul>	*	Datatype Kind Transactional	File ID FI_DOC	Primary	Primary CPUDT	Date Fie	ld
Tables     Subset Synce		🕄   📇 😽 🛗 Linkages [ Display M	🕒 🗗 🗸 lode ]		2		
<ul> <li>Data Snap</li> <li>Scenarios</li> <li>Export Memory Config</li> <li>FI - G/L ACCOUNT FIGURES</li> <li>FI - GL ITEMS (FAGLFLEX)</li> </ul>		Recipient DT CO - LINE ITEMS			VBFA FI.	Inactive	
		FI - CONSOLIDATIO	) DNS GLELEX )				
GL TOTALS (FAGLFLEX)      GI - GMIA      GH - GMIA		FI - MATERIAL LED FI - PCA (GLIDXA)	GER (CKMI1)				
<ul> <li>Image: Provide the second secon</li></ul>		FI - PROFIT CENTE FI - REVERSAL FIN	R DOCS ANCE DOCS				

To run this utility, just check the 'Deactivate Linkages' box and select 'Execute'. It is not even necessary to specify which data types to analyze for deactivation; instead, <u>all</u> Recipient Data Types are automatically analyzed.



Here is what the output looks like after having executed the Deactivate Linkages utility (Fig. 2.5).



#### **Remove Non-Existent Tables**

Gold Client is delivered with many tables already pre-configured, so this utility is used to remove tables from both the Client Construct and Data Echo frameworks that do not exist within a customer's system. The tables being updated by this utility all reside within the Gold Client namespace (/HTG/\*).

To run this utility, just check the 'Remove Non-Existent Tables' box and select 'Execute'.

Remove Non-Existent Tables

Here is an example of what the output looks like after having executed the Remove Non-Existent Tables utility (Fig. 2.6).

	Figure 2.
Gold Client - Synchron	nise TABLES1 and TABLINK entries
Gold Client - Synchronise TA	BLES1 and TABLINK entries
START OF REPORT	FD ·
/HTG/ZTABLEMAP /HTG/ZTABLEMAP /HTG/ZTABLEMAP	ZPHDEMO_ATTRTAB2 ZRPM_STATUS ZAH_DANGER
======================================	

#### Initialize /HTG/ number ranges

To use Gold Client, it requires that a few different number ranges exist. The number range object themselves are delivered as part of the Gold Client code, but the ranges themselves must then be defined in **<u>each client</u>** where Gold Client will be used.

To run this utility, check the 'Initialize /HTG/ number ranges' box and select 'Execute' to reach the subsequent screen.

✓ Initialize /HTG/ number ranges

When displaying the selection screen, the default entry is 'Report Only' which is the same as running the program in test or simulation mode. Select the 'Update Database' option to define the actual number ranges (Fig. 2.7).

Figure 2.7

Insert /HTG/* NRIV entries if not present
( Execute
Processing Options
<ul> <li>Report Only</li> <li>Update Database</li> </ul>

The following outputs will appear based on the various circumstances: if the number ranges have already been defined (Fig. 2.8); if they have not yet been defined (Fig. 2.9); or they are defined when executing the program (Fig. 2.10).

If the ranges already exist and the user selects 'Update Database' no changes will occur since they only need to be defined once.

						Figure 2.8
Object name	Subobj.va	No	Year	From number	To number	Description
/HTG/COUNT		01		2000001	99999999	Object already exists
/HTG/EXPID	DS	1		1001	9000	Object already exists
/HTG/EXPID	DW	1		9900	9999	Object already exists
/HTG/EXPID	EC	1		0001	0899	Object already exists

Object name	Subobj.va	No	Year	From number	To number	Description
/HTG/COUNT		01		2000001	99999999	Object does not exists
/HTG/EXPID	DS	1		1001	9000	Object does not exists
/HTG/EXPID	DW	1		9900	9999	Object does not exists
/HTG/EXPID	EC	1		0001	0899	Object does not exists

Object name	Subobj.val	No	Year	From number	To number	Description
/HTG/COUNT		01		2000001	99999999	Object created
/HTG/EXPID	DS	1		1001	9000	Object created
/HTG/EXPID	DW	1		9900	9999	Object created
/HTG/EXPID	EC	1		0001	0899	Object created

#### **Configure Master Data Tables**

This utility is used to add various Condition tables (pricing, output, KOT\*), HR infotypes, and custom tables to the Client Construct framework so that the master data stored in these tables can be successfully copied. Alternatively, tables can be added to the framework manually.

To run this utility, just check the 'Configure Master Data Tables' box and select 'Execute'.

✓Configure Master Data Tables

The tables being updated by this utility all reside within the Gold Client namespace (/HTG/\*). Here is an example of what the output looks like after having executed the Configure Master Data Tables utility (Fig. 2.11).

					Figure 2.11
START OF REPORT					
/HTG/ZTABLEMAP:	BILLING	OUTPUT	CONDITIONS	B000	
/HTG/ZTABLEMAP:	BILLING	OUTPUT	CONDITIONS	B001	
/HTG/ZTABLEMAP:	BILLING	OUTPUT	CONDITIONS	B002	
/HTG/ZTABLEMAP:	BILLING	OUTPUT	CONDITIONS	B005	
/HTG/ZTABLEMAP:	BILLING	OUTPUT	CONDITIONS	B006	
/HTG/ZTABLEMAP:	BILLING	OUTPUT	CONDITIONS	B007	
/HTG/ZTABLEMAP:	BILLING	OUTPUT	CONDITIONS	B008	
/HTG/ZTABLEMAP:	BILLING	OUTPUT	CONDITIONS	B009	
/HTG/ZTABLEMAP:	BILLING	OUTPUT	CONDITIONS	B010	
UTO/ZTODLEMOD.	DTLL TNO	AUTOUT	CONDITIONS	DO44	

Here is a sample result of executing this utility where the tables have been added to the Client Construct data types (Fig. 2.12).

Master Data Type	BILLING OUTF	OT CONDITI	SNC
Master Data Tables			
Table Name		Exclusion	Exclusion R
B000			
B001			
B002			
B005			
B006			
B007			
B008			
B009			
B010			
0044			

#### **Configure Custom Table**

This utility enables customers to easily incorporate custom tables into the Data Echo framework. The end result is typically a joining or mapping between standard SAP tables and custom tables. Once the join is complete, subsets of data stored in these tables can be successfully copied using the Data Echo functionality.

The tables being updated by this utility all reside within the Gold Client namespace (/HTG/\*). Alternatively, custom tables can be added into the Data Echo framework manually.

To run this utility, check the 'Configure Custom Table' box.

Configure Custom Table

Upon doing so, a Namespace field will appear with values 'Z' and 'Y' defaulted. The user can input additional table namespaces if required; for example, an organization may have their own custom namespace that could be added.

✓ Configure Custom Table	Namespace	Z		

Here is an example of what the output looks like after having executed the utility (Fig. 2.13).

				Figure 2.13					
Auto	Auto Config Utility								
916	🕄   🔂   🚢 🚏   🛗 📸   🚣 Accept – 🐺 Exclude – 🏭 Field Exceptions								
Custo	om Table Repo	ort							
Select	Custom Table	Data Type	Link Table	Link Fields					
	ZDS400_POS	MM - PURCH DOCS FROM WORK ORDERS	EKPO	EBELN-EBELN,EBELP-EBELP					
	ZDS400_POS	MM - PURCHASING CONTRACTS	EKKO	EBELN-EBELN					
	ZDS400_POS	MM - PURCHASING DOCS FROM PREQ	EKKO	EBELN-EBELN					
	ZDS400_POS	MM - PURCHASING DOCS FROM PREQ	EKPO	EBELN-EBELN,EBELP-EBELP					
	ZDS400_POS	MM - PURCHASING DOCUMENTS	EKKO	EBELN-EBELN					
	ZDS400_POS	MM - PURCHASING DOCUMENTS	EKPO	EBELN-EBELN,EBELP-EBELP					
	ZDS400_T001	CA - VENDOR MASTER	LFB1	BUKRS-BUKRS					
	ZDS400_T001	SD - CUSTOMER MASTER	KNB1	BUKRS-BUKRS					
	ZDS400_VBAK	SD - CONTRACTS	VBAK	VBELN-VBELN					
	ZDS400_VBAK	SD - INQUIRIES FROM SALES DOCS	VBAK	VBELN-VBELN					
	ZDS400_VBAK	SD - QUOTATIONS FROM SALES DOCS	VBAK	VBELN-VBELN					

Using the output, it's possible to review which custom table could be potentially joined to which SAP standard table based on the utility's comparison of **matching data elements**. An example of this is highlighted (Fig. 2.14) where the link between custom table ZDS400\_POS and standard table EKKO using common fields EBELN to EBELN is proposed.

#### Figure 2.14

Figure 2.15

Auto Config Utility								
916	∰ M    ₹ ≜	Accept		🔝 Field Exception	ons			
Custom Table Report								
Select	Custom Table	Data Type		1	Link Table	Link Fields		
	ZDS400_POS	MM - PURCH	I DOCS FROM	WORK ORDERS	EKPO	EBELN-EBELN,EBELP-EBELP		
	ZDS400_POS	MM - PURCH	ASING CONTI	RACTS	EKKO	EBELN-EBELN		
	706400 006	MANA DUD.CI	LACTALC DOCC	EDOM DDEO	FILLO	EDELNI EDELNI		

To create the join between the proposed tables, select the relevant entries and then click the 'Accept' button (Fig. 2.15).

Auto Config Utility		
3   2 2   4 7   11 14	🚰 Accept	

**Caution:** It's important to review each proposed table link critically as linking in custom tables *incorrectly* or *inefficiently* <u>can impact the performance of data exports</u>. If unsure whether to proceed with one or more table links, consider seeking advice from either your team's internal ABAP resources and/or the Qlik support team.

Upon accepting one or more links between custom and standard tables, an output is provided displaying the outcome (Fig. 2.16).

			Figure 2.16
Auto Config Utility			
START OF REPORT			
Custom Table Configuration			
Custom Table	Data Type	Link Table	Link Fields
VIT_01ASS	CA - ASSET MASTER	ANLA	BUKRS-KEY_EXT2,ANLN1-KEY_EXT3
Tables Excluded			
YIT_01C0S YIT_02C0S YIT_03C0S ZSAFI			

The actual result of executing this utility is reflected in this example where custom table YIT\_O1ASS was linked to table ANLA using the proposed common fields within Data Echo data type CA – ASSET MASTER (Fig. 2.17).

Gold Client Data Framework         Create       Copy       Delete       Master Data Type       Transaction Data Type       Prima         Data Framework       CA - ASSET MASTER       Data Type       Data Type       Datatype Kind       File ID       Prima	y Data
Create Copy Delete Master Data Type Transaction Data Type Prima          Data Framework         Data Type         CA - ASSET MASTER         Data Type         CA - APPLICATION LOG DETAILS	y Data
Data Framework	v Prin
CA - APPLICATION LOG DETAILS     Datatype Kind File ID Prima	y Prin
CA - APPLICATION LOGS     Master Data CAASET	ERD
CA - APPROPRIATION REQUESTS     CA - ASSET MASTER	<b>*</b>
• Inables     Tables [ Display Mode ]       • Inkages     • Tables [ Display Mode ]       • Value     • Tables [ Display Mode ]       • Source     • Hd Flg       • Source     • Hd Flg       • Source     • Hd Flg	Data
Data Snap     O Scenarios	
Export Memory Config      CA - ASSET MASTER (ORIGIN)      Ca - ASSET MASTER (ORIGIN)	602
CA - ASSORTMENT MODULES  CA - BATCH CA - BATCH JOB VARIANTS  YIT_OTASS-ANLA	
Image: CA - BATCH JOBS       Table Fid       Source Field         Image: CA - BATCH JOBS (PREDECESSORS 2)       ANLN1       KEY_EXT3         Image: CA - BATCH JOBS (PREDECESSORS 2)       BUKRS       KEY_EXT2	

There may be table joins that you want to exclude from future executions of the Configure Custom Table utility (for whatever reason). These proposed joins can be eliminated by selecting the appropriate entries and selecting the 'Exclude' button (Fig. 2.18).

Auto Config Utility	
🕄   🗟 🗟   🖴 🐬   🎁 🖓   🖓 Accept	Prese Exclude

Some proposed joins may use only a single data element, and these are typically hierarchical objects; Company Code, Plant, and Sales Organization are just a few examples. The Qlik team would never recommend creating a join using just one of these lone fields as it is far too generic and would likely cause Gold Client to export substantial amounts of data from the relevant custom table.

To define a list of lone data elements that the program should exclude, select the 'Field Exceptions' button (Fig. 2.19). In the table that appears on the subsequent

screen, add data elements as required; save changes and exit the table (Fig. 2.20). The report must be executed again for these new entries to be considered.

To be clear, the program does not ignore these data elements entirely, just when they are **the only common data element shared between the two tables**.

					Figure 2.19
	Auto Config Utility				
	9 6 4 7 6	Accept	P Exclude	🔝 Field Exceptions	
					Figure 2.20
Change	View "Fields to be excl	luded if a	those are a	the only match	": Overv
6 New Ent	tries 🗈 🖶 🗊 🖡 🖡 🖡				
Fields to be	excluded if those are the only match				
Data elem	nent	- -			
		•			

### Custom Table Discovery

This program can be used to try and identify custom tables within a given system that might need to be incorporated into the Gold Client configuration. The primary purpose is to arm users with information about which tables are in a given system that may be relevant for incorporation.

The default inputs are for those tables named Z\* and Y\* and have a delivery class of 'A' (Application Data). The user can add/edit the Table Name and Delivery Class inputs as required (Fig. 3.0).

The '*Hide if in Data Echo'* and '*Hide if in Client Construct'* options can be used to exclude those custom tables which have already been incorporated into one or both of the Gold Client configurations.

		Figure 3.0
Report Zee tables	s, key fields and rel	ated data elements
Ø		
Table Name	[×] Z*	to 💽
Delivery class	A	to 📄 🖉 📑
✔ Hide if in Data Echo		Trz Multiple Selection for Table Name
Hide if in Client Construct		
		Select Single Values (7) Select Ranges Exclude
	Maintain Excluded Tables	
		O Single value
		Z*
		X Y*

The screen also has an option to maintain a list of tables that should be excluded from the report each time it is executed. Selecting the 'Maintain Excluded Tables' button will launch a new screen where tables can be excluded from the /HTG/ZEE report (Fig. 3.1).

		Figure 3.1
Change View "Zee tables to e	exclu	de from /HTG/ZEE query": Overview
😚 New Entries 👔 🖶 📭 💽 🚯		
Zee tables to exclude from /HTG/ZEE query		
Table Name	11	
	*	

The report output lists the custom Table Name, Delivery Class, Short Description, Table Position, Field Name, Data Element, and Long Field Label (Fig. 3.2). This information may be very useful in identifying where to place the custom tables into the Gold Client configuration.

The output only shows the key fields for each custom table, and skips the displaying of the first key field, MANDT, or the Client field.

						Figure 3.2
Report Zee tables	s, k	ey fields and related da	ta el	lements		
311 770	45	🗟 👿 🔚 🔠 🗉				
Table Name	D	Short Description	TabP	Field Name	Data element	Long Field Label
ZACT_NAMES	Α	IMG activity names	2	ACTIVITY	CUS_IMG_AC	IMG Activity
ZADHOCXPORT	Α	Import/Export Structure for ADHOC E	2	RELID	INDX_RELID	Area
	Α		3	ZPROG	CPROG	CALL program
	Α		4	SRTF2	INDX_SRTF2	Counter
ZAH_DANGER	Α	Hazardous material number	2	DANGER_NO	SDANGER_NO	Haz. material number
ZAH_MC	Α	Table for multiple choice quiz	2	COURSE	ZAH_MC_COURSE	Course
	Α		3	TOPIC	ZAH_MC_TOPIC	Topic for question
	Α		4	LANGUAGE	LANGU	Language Key
ZAH_VOTE	Α		2	UNAME	UNAME	User Name
ZAIF_D01_SIDX_01	Α	Single index table for DEMO BUPA_IN	2	MSGGUID	GUID_32	GUID 16
ZARIBA_AN_ERPINV	Α	Stores invoices created in ERP and wh	2	BUKRS	BUKRS	Company Code
	Α		3	BELNR	XBLNR	Reference
	Α		4	GJAHR	GJAHR	Fiscal Year

### Setup Confirmation

This utility is primarily used by the Qlik team prior to deploying Gold Client in a customer's system to help ensure that the system and related items are ready; however, it may also be useful for customers who want to deploy Gold Client to other systems where it did not exist previously and confirm that everything is setup accordingly.

This program does not require any user inputs. Selecting this program triggers its execution immediately. The total runtime should be less than a minute.

Perhaps the most useful part of the report's output is listed at the top (Fig. 3.3). If there were any issues found with the various configuration items, the status would be red. Freely contact Qlik support if assistance is required with any items displaying a red / error status.

		Figure 3.3
Automatic Configurati	ion C	onfirmation utility
g ltmmt. I.a		
Configuration checklist		
Configuration Name	Status	Message
Consolidation Route	000	Consolidation routes are configured in the current system.
Write to File		CONFIG_TEST file was succesfully writen.
Read From File		Succesfully read the file.
Authorization to ZGOLD	<b>00</b>	Authorization check passed.
Client Construct Config	<b>00</b>	Client Construct Config exists in the current system.
Data Echo Config	<b>00</b>	Data Echo Config exists in the current system.

The remaining part of the output is more informational and is useful for the Attunity team prior to deploying Gold Client on the customer's system (Fig. 3.4).

Figure 3	3.4
----------	-----

Database Size					]
Name:	DEFAULT	Last analysis:	06/06/2019	07:21:11	
DB system:	ORA	Filling degree:			
Size:	<b>481,48</b> GB	Total size:		996,09 GB	
Free Space:	33,06 GB	Total free space:		547,67 GB	
Used:	93 %	Total used:	Г	45 %	
			L	L	
Host data					
Operating system	Linux				
Machine type	x86_64				
Server name	sap-gct_G	CT_00			
Platform ID	390				
Database data					
Database Syatem	ORACLE				
Release	12.1.0.2.	0			
Name	GCT				
Host	sap-gct				
Owner	SAPSR3				
System Data					
Logical System	T90CLNT09	Component	version EH	P8 FOR SAP ERP 6	9
Standard Currency	EUR				
Client Export Post Pro	cessing				
Date Time	Source Statu	s Text	Profile	Mode	Test Mode
00:00	:00				

# Data Wave

The Data Wave folder organizes all of the configuration programs specific to Data Wave functionality in one location. Most of these programs can be accessed via the Gold Client configuration menu or via the Data Wave configuration menu. The programs in this folder are documented independently; reference the user guide named <u>Data Wave Setup and Configuration</u> which can be located on Qlik's customer support website.

# **Client Construct Framework**

This utility serves as the entrance point to where all configuration maintenance can be performed in relation to the Client Construct functionality within Gold Client (Fig 4.0).

Due to the importance of this configuration and the significant purpose it serves, a separate user guide exists. For more information and support, see the <u>Client</u> <u>Construct 8.6 User Guide</u> which can be located on Qlik's customer support site.

		F	igure 4.0		
Display View "Master	Display View "Master Data Types": Overview				
🥸 🗈 🖪 🗗					
Dialog Structure	Master Data Types				
Master Data Types	Master Data Type	Data Wave	111		
• Master Data Tables	ASSET MASTER				
	BANKING MASTER	4	-		
	BILL OF MATERIALS	$\checkmark$			
	BILLING OUTPUT CONDITIONS	4			
	BUSINESS PARTNERS	4			
	CAPACITY PLANNING	4			
	CASH & LIQUIDITY MANAGEMENT	<b>v</b>			
	CENTRAL ADDRESS MASTER	$\checkmark$			

### Data Echo Framework

This utility serves as the entrance point to where all configuration maintenance can be performed in relation to the Data Echo functionality within Gold Client (Fig. 4.1).

Due to the importance and complexity of this configuration, and the significant purpose it serves, a separate user guide exists. For more information and support, see the *Data Echo Advanced Config 8.6 User Guide* which can be located on Qlik's customer support site.

					Figure 4.1
Gold Client Data Framework					
Create Copy Delete Primary Data Type	Waster Data Type	Transaction Data Type	😽 Display All	Classic View	🙀 Data Types by Tags
Data Framework					
🝷 🛅 Data Type					
CA - ASSET MASTER					
CA - BUSINESS PARTNERS					
CA - CASE MANAGEMENT					
CA - EQUIPMENT DATA					
CA - ORDERS MASTER (AUFK)					
CA - VENDOR MASTER					
FI - FINANCE DOCUMENTS					
FI - PAYMENT RUNS					
R - EMP MAST WITH PAY POSTING					
MM MATERIAL DOCUMENTS					
PM - MAINTENANCE PLANS					
PP - PLANNED ORDERS					
PROJECT DEFINITIONS					
• M - INSPECTION LOTS					
• 🖲 OM - QUALITY NOTIFICATIONS					
SD - CUSTOMER MASTER					
SD - SALES DOCUMENTS					
WM - TRANSFER REQUIREMENTS					
WM - WAREHOUSE MANAGEMENT					

#### Data Type Hierarchy Report

With many different Data Types and the various linkages that can exist among them, it can be very complicated to identify what data is being exported when using a particular Data Type. The Data Type Hierarchy Report can easily identify all of the different Data Types analyzed during the export process.

For example, to identify all recipient Data Types used by Sales Documents, execute the Data Type Hierarchy Report for data type SD – SALES DOCUMENTS (Fig. 5.0).

		F	igure 5.0
Data Ech	no Data Type Hiel	rarchy Report	
🚱 Execute	💖 Data Type Manager		
Data Type		SD - SALES DOCUMENTS	

The report output displays all recipient data types in a hierarchical (top-down) format for the given data type. The default option is to display only those data types which are set as 'active' within the Data Echo Framework. To see all links within the hierarchy (both active and inactive), select the 'Inactive Linkages Displayed' radio button; the output will automatically refresh upon its selection. Freely select the 'Active Linkages Only' radio button and the output will refresh accordingly (Fig. 5.1).

Within the output, related data types can be expanded individually by selecting the relevant folder, or all related data types can be expanded by selecting the 'Expand subtree' icon. Likewise, the data types can be collapsed individually by selecting the relevant folder, or all related data types can be collapsed by selecting the 'Collapse subtree' icon (Fig. 5.1).

Data types that have a document icon next to them represent those data types which have <u>no recipient</u> data types related to them; see data type CA – CHANGE DOCUMENTS as an example. Data types that have a folder icon next to them represent those data types which have <u>one or more recipient</u> data types related to them; see data type FI - REVENUE RECOGNITION as an example (Fig. 5.1).

The 'Dupl\_Flag' (Duplicate Flag) column indicates those Data Types which are linked more than once. The 'Inactive' column indicates whether or not the Recipient data type is set as an inactive link from the Provider Datatype within the Data Echo Framework (Fig. 5.1).

Note that the Date Type can be changed directly from the output screen. If this action is taken, select the 'Refresh' button in order to update the report's output.

			Figure 5.1	
Data Echo Data Type Hierarchy R	eport			
🔁 Refresh 🛛 🦻 Data Type Manager				
Data Type SD - SAL	ES DOCUMENTS	1	]	
<ul> <li>Active Linkages Only</li> </ul>				
○ Inactive Linkages Displayed				
	Dupl Flag	Inactive		
T SD - SALES DOCUMENTS	b up [] h ug	Indecire		
CA - CHANGE DOCUMENTS				
• 🖹 CA - OUTPUT STATUS				
CA - SERIAL NUM FOR SALES ORDERS				
• 🖹 CA - TEXT				
• FI - CASH MGMT FOR SD DOCUMENTS				
FI - REVENUE RECOGNITION				
LINK - SALES DOC TO RESERVATIONS				
LINK - SALES DOCS TO INQUIRIES				
LINK - SALES DOCS TO PROD ORDERS				
LINK - SALES DOCS TO QUOTATIONS				
LINK - SALES ORDER ITEMS				
LINK - SD DOC TO CUSTOMER MASTER				
MM - MATERIAL DOCUMENTS				
MM - PURCH DOCS FROM SALES DOCS				
SD - DELIVERIES				
• E SD - DOC FLOW (VBEA)				
SD - SALES DOCS TO CREDIT MEMO				
SD - SALES DOCS TO DEBIT MEMO				
SD - SALES DOCS TO RETURNS				

Users can also reach the Data Type Manager function from this report, either from the input screen (Fig. 5.2) or the output screen (Fig. 5.3). Selecting it from either location will direct the user to another screen where the configuration relevant to the given Data Type can be displayed. If the user has the proper authorizations, they would be able to deploy changes to this config, but if not, then the config would be display only. For more information, reference the <u>Gold Client Data Echo Advanced</u> <u>Configuration Guide</u>.

			Figure 5.2
Data Ech	ho Data Type Hiel	rarchy Report	
🚱 Execute	💖 Data Type Manager		
Data Type		SD - SALES DOCUMENTS	

Figure 5.3

Data Echo Data Type Hierarchy Report			
Refresh	😵 Data Type Manager		
Data Type		SD - SALES DOCUMENTS	
<ul> <li>Active Linkages Only</li> <li>Inactive Linkages Displayed</li> </ul>			

### **Tables Missing Field Relations**

This utility provides a quick way to check if any table relationships within the Data Echo configuration are missing their related common field entries. This program does not provide a way to fix the issue; instead, the user needs to add the missing fields within the Data Echo framework itself.

There is no input screen so selecting this executable immediately initiates the check. If issues are found, the output will look like this (Fig. 5.4), and if no issues are found, the output will look like this (Fig. 5.5).

			Figure 5.4
Missing Common Field	ls for Table Relations		
3 2 7 11 2			
Data Type	Table Name	Source Table	
CA - BUSINESS PARTNERS	BUT010	BUT000	
			Figure 5.5
			r iguro o.o
Missing Common Field	ls for Table Relations		
Data Type	Table Name	Source Table	
	_		

### Set Data Snap Record Limits

This utility provides an easy way to update the maximum number of records that is allowed when executing Data Snap exports.

Input the respective Data Type and then 'Execute' (Fig. 5.6).

	Figure 5.6
Set Data Snap Record Limits	;
•	
Data Type	[]a
Execute	

Update the value stored in the 'Data Snap Rec. Limit' field as required (Fig. 5.7). Save changes and exit when done.

				Figure 5.7
Change View "Data Type": Overview				
🦻 New Entries 🗋 🖶 🖙 🕃 🕵				
Dialog Structure	Data Type			
Data Type	Data Type	DT Kind	File ID	Data Snap Rec. Limit
Tables     Fields	SD - SALES DOCUMENTS	Transactional	▼ SD_SD_	1.000

## Maintain Data Type Tags

This utility provides the ability to define tags and then assign them to one or more Data Types. The value of this activity is that it provides Gold Client users another way of searching for various Data Types and do so with values that are custom and relevant to the team. Some possible examples of tags can be seen below (Fig. 5.8).

	Figure 5.8
Tag definition	
Tag ID Des	cription
D-TYPE NOT RELEVANT This	data type is not relevant to our organization
D-TYPE NOT VALIDATED Copy	ing data for this Data Type is being validated now
DATA TYPE VALIDATED Copy	ing data for this Data Type has passed validation
HIGHEST PRIORITY Valid	ating this data type has the highest priority!
TESTING IN PROGRESS test	in progress

Select the 'New Entries' button and then input one or more Tag IDs and descriptions as required (Fig. 5.9).

			Figure 5.9
New Entries: Overview	v of Added Ent	ries	
🧐 🖥 🖺 🖪 🖪			
Dialog Structure	Tag definition		
Tag definition	Tag ID	Description	
	·		

Select the row for a given Tag and then choose the 'Tag by Data type' folder from the Dialog Structure (Fig. 5.10).

		Figure 5.10
Dialog Structure	Tag definition	
Tag definition	Tag ID	Description
• I ag by Data type	D-TYPE NOT RELEVANT	This data type is not relevant to our organization
	D-TYPE NOT VALIDATED	Copying data for this Data Type is being validated now
	DATA TYPE VALIDATED	Copying data for this Data Type has passed validation
	HIGHEST PRIORITY	Validating this data type has the highest priority!
	TESTING IN PROGRESS	test in progress

Select the 'New Entries' button and then input one or more Data Types as required (Fig. 5.11).

			Figure 5.11
New Entries: Overview	v of Added Ent	ries	
🥸 <b>5</b> 🖪 🖪 🖪			
Dialog Structure Tag definition	Tag ID	DATA TYPE	VALIDATED
• 🛅 Tag by Data type	Tag by Data type		
	Data Type		
			<u></u> α ≁
			<b>_</b>

An example of results once Data Types have been entered (Fig. 5.12).

Dialog Structure Tag definition	Tag ID DATA TYPE VALID	DATED
• <del>声</del> Tag by Data type	Tag by Data type	
	Data Type	
	MM - MATERIAL MASTER	-
	MM - PIR	<b>T</b>
	MM - PURCHASING DOCUMENTS	

Once a tag has been defined, it is possible to display and maintain tag assignments within the Data Echo framework (Fig. 5.13 and 5.14). It is not possible to define tags from this perspective, only to assign them.



Figure 5.13

Figure 5.12

Figure 5.14

MM - MATERIAL MASTER				
DT Kind	File ID	Primary	Primary Date Field	
Master Data	MMMATM	<b>v</b>	ERSDA	
Tags for Data Type [ Display Mode ]				
Tag ID DATA TYPE VALIDATED				

Once a tag has been assigned to at least one Data Type, it is possible to search for them. From the main Gold Client screen, select Data Snap. For the field named 'Select Data Type' use the search help function (Fig. 5.15) and select the search help named 'Data Type by Tags' (Fig. 5.16); an example of search help results (Fig. 5.17).

		Figure 5.15
Data Snap		
🦻 Data Type Manager		
Select Data Type:	SD - SALES DOCUMENTS	

			Figure 5.16
🔄 Datatype with special Searc	ch Help (1)		
Data Type Search	Data Type by Table	Data Type by Tags	Data T
Tag ID		] <b>_</b>	·
Data Type			
Maximum No. of Hits	500		

- Iguit	
🔄 Datatype with special Search Help (1) 17 Entries found	X.
Data Type by Table         Data Type by Tags         Data Type by Flow	2
$\nabla$	
Tag ID Data Type	
D-TYPE NOT RELEVANT TR - BANKING STATEMENTS	
D-TYPE NOT RELEVANT TR - CFM TRANSACTIONS	
D-TYPE NOT RELEVANT TR - QUOTATION PRICE INFORMATION	
D-TYPE NOT RELEVANT TR - SECURITIES ACCOUNT MASTER	
D-TYPE NOT VALIDATED CA - ASSET MASTER	
D-TYPE NOT VALIDATED CA - ORDERS MASTER (AUFK)	
D-TYPE NOT VALIDATED FI - FINANCE DOCUMENTS	
DATA TYPE VALIDATED MM - MATERIAL MASTER	
DATA TYPE VALIDATED MM - PIR	
DATA TYPE VALIDATED MM - PURCHASING DOCUMENTS	
HIGHEST PRIORITY CA - ORDERS MASTER (AUFK)	
HIGHEST PRIORITY FI - FINANCE DOCUMENTS	
HIGHEST PRIORITY MM - PURCHASING DOCUMENTS	
HIGHEST PRIORITY SD - SALES DOCUMENTS	
TESTING IN PROGRESS AB - AGENCY BUSINESS DOCUMENTS	
TESTING IN PROGRESS CA - CHANGE DOCUMENTS	
TESTING IN PROGRESS PM - MAINTENANCE PLANS	

#### **S4 Exclude Fields**

This functionality has been specifically developed for use in HANA S4 systems. The reason is due to how S4 calculates values for some tables and fields on the fly -- one example is for various material stock quantities. Another way to think about this difference is that the values in these fields are no longer just attributes stored within a given table as they were in previous SAP versions.

The Qlik team has determined that exporting these calculated fields <u>may</u> cause performance/stability issues because of the calculations that are performed by the S4 application, and also that there is no value in copying them from the source to the target anyhow since the application will derive the calculated value. Therefore, it is necessary to exclude some fields from being included in the export and import processes. This is entirely different to how Gold Client has historically worked in that <u>all columns</u> on a table were <u>always included</u> in the export and import, and the user had no control to manipulate this outcome.

This executable takes the user to a customizing (SM30) type of table where relevant tables and fields that need to be excluded during copy processing can be added (Fig. 5.18). The Qlik team should be able to suggest some entries that belong in this table so freely submit a support case to the Qlik team for discussions as required.

Figure 5.18

New Entries: Overview of Added Entries	
<sup>6</sup> ≫ ₽ ₽ ₽ ₽	
Gold Client Table and Field Exclude List	
Table Name	Field Name

Maintaining entries in this table requires the user to have a role assigned which contains Gold Client authorization activity '85'. This is the same activity required in order to perform maintenance to the Data Echo framework. Please reference the <u>Gold Client 8.6 Security</u> document for more details.

# Config Download/Upload (JSON)

As the name suggests, this program is used to download and upload the Gold Client configuration. The intended use case for this program is to streamline support for customers who may need Qlik team assistance with updating their configuration; however, it can also be used to simply backup the configuration to file in case the need arises for restoration. Please see the primary use case "flow" below in case useful.

- Customer's User/Admin downloads their Gold Client config to file
- User/Admin sends config file to Qlik Support team via support case
- Qlik Support team uploads this config to internal systems
- Qlik Support team performs updates as required
- Qlik Support team downloads this updated config to file
- Qlik Support team provides file to the User/Admin via support case
- User/Admin uploads config into their respective system(s)

To understand the true benefit of this solution, this same process has previously required the need to generate transports and to pass them back and forth between the customer's team and the Qlik team which, because transports were involved, typically required the involvement of the customer's Basis team since access to the operating system was required. This solution removes some of those potential bottlenecks thus helping streamline the process.

On the following pages, the introduction section shares useful and important information regarding all of the various settings and options available within this program; there are subsequent sections for initiating the download and upload processes.

#### **Important Notes:**

This program requires Gold Client security activity '85' which is the same one that users must have in order to perform maintenance to the Client Construct and Data Echo frameworks. It is therefore suggested that this download / upload program be accessed only by the team's administrators.

This program can be executed in Production systems; however, it contains important logic that restricts the content which can be downloaded and uploaded to **only those tables that reside within the /HTG/ (Gold Client) namespace**. This safeguard is in place so that users cannot accidentally or intentionally import or overwrite data in their Production system.

The Qlik team recommends using this program with some caution because if it were used incorrectly or maliciously, it could significantly impact a team's "golden" version of their Gold Client config; however, be mindful that this program can also be very useful in order to <u>backup and restore a team's configuration</u>.
Figure 5.19

### Introduction to Functionality

The initial Config Download/Upload (JSON) screen appears like this (Fig. 5.19).

- The 'Download' action is set by default
- The local path and filename default to C:\GoldClient\GoldClientConfig\_SID###.txt where the System ID and Client values are based on the system-client in which the user is signed in. In this example (Fig. 5.19), the system is EST and the client is 800.
- The text box shares some content around the logic that is used in order to determine which Gold Client tables are downloaded and/or uploaded

Config Download/Upload (JS	SON)
Execute	
File Action	
<ul> <li>Download</li> </ul>	
OUpload	
Target or Source	
Local path and filename	C:\GoldClient\GoldClientConfig_EST800.txt
Program Notes	
The Gold Client configuration downloaded by th	is program is sourced from
the Client Construct data type named:	
GOLD CLIENT ALL CONFIGURATION	

If the 'Upload' action is set by the user, the screen updates accordingly and introduces to the user two additional options (Fig. 5.20).

- "Table Update Instructions"
  - Delete all recs, then Insert
    - This option should be selected if a complete synchronization is the desired outcome as the program will purge all records from the relevant Gold Client config tables and then insert the records stored within the file
    - This is the default setting
  - Insert new, Modify existing
    - This option should be selected if only new config should be added and only changed config should be updated. All other config should remain as-is.
    - Selecting this setting may be useful if during the time that the Qlik team was enhancing the customer's config, that the customer was also deploying config changes within their system that would be lost when using the "Delete all recs, then Insert" option.
  - "Post-Processing Options"
    - Remove Non-Existent Tables: This setting will execute a Gold Client program that is used to purge tables from the Gold Client configuration that does not exist in the respective system's data dictionary (DDIC).
    - Using a hypothetical example, the Qlik team adds 100 new tables to a customer's Gold Client configuration through the update process. This

config is subsequently uploaded into the customer's system; however, of these 100 tables, 20 do not exist within the customer's system and so should be purged from their Gold Client config. Running this program will check and remove those tables accordingly. This would most likely occur when a customer is running an older version of SAP, but there may be other reasons for this outcome to occur.

 Note: it is not possible to run only this purging program from the Config Download/Upload (JSON) screen; however, it can be executed standalone from elsewhere within the Configuration menu when necessary. Go to the section named <u>Installation Setup</u> within this document for details.

	Figure	ə 5.20
Config Download/Upload (JS	SON)	
Execute		
File Action		
ODownload		
⊙ Upload		
Table Update Instructions		
<ul> <li>Delete all recs, then Insert</li> </ul>		
○Insert new, Modify existing		
Target or Source		
Local path and filename	C:\GoldClient\GoldClientConfig_EST800-doc1.txt	
Post-Processing Options		
Remove Non-Existent Tables		
Program Notes		
The Gold Client configuration downloaded by this	s program is sourced from	
the Client Construct data type named:		
GOLD CLIENT ALL CONFIGURATION		

### Download process

- 1. In order to execute a download, the user simply needs to confirm or update the file path and/or name and then click the 'Execute' button
- 2. Since the program is attempting to write a file to the user's local directory, this window may appear (Fig. 5.21). The user will need to select 'Allow' for the program to continue or otherwise select 'Deny'.
  - Selecting the latter option will cancel the process and the config will not be written to file
  - This window may not appear if the user has previously selected the 'Remember My Decision' checkbox
- 3. Once the program completes processing, an output appears on the screen; a sample of that output is displayed here (Fig. 5.22)
  - The output shows the tablename, the number of records written to file, and a status
  - The statuses are limited to 'SUCCESS' and 'NO DATA'; the latter status simply indicates that the table contained no data and so none was written to file; this is not an unusual result
  - If for some reason you anticipated a different outcome, it is recommended that you contact the Qlik team for support
- 4. Go to the respective file directory and open the file in case you wish to display its contents. If needed, send the file to the Qlik support team if the config is to be updated by them.

	Figure 5.21
SAP GUI Security	×
The system is trying to create the file	
C:\GoldClient\GoldClientConfig_EST800-doc1.txt	
in the directory	
C:\GoldClient\	
Do you want to grant the permission to modify the parent directory and all its subdirectories?	
□ <u>R</u> emember My Decision	
Allow Deny	

Figure 5.22

### DOWN ### Load			
914770	) 🐴	🕒 🛛 🔒	
Table Name	Rec. Ct.	Status	
/HTG/BDLS	187	SUCCESS	
/HTG/COMPR_EXCP	0	NO DATA	
/HTG/CONVERSION1	0	NO DATA	
/HTG/EWM_TABMAP	0	NO DATA	
/HTG/GCSMAPTABLE	0	NO DATA	
/HTG/GCSPARMETER	4	SUCCESS	
/HTG/GCSTIMESTMP	17	SUCCESS	
/HTG/GCS_ALTMAP	71	SUCCESS	
/HTG/GCS_CHG_DOC	37	SUCCESS	
/HTG/GCS_DW_PPU	0	NO DATA	
/HTG/GCS_MAP_RFC	0	NO DATA	
/HTG/GCS_TAGS	4	SUCCESS	
/HTG/GCS_TAG_DT	5	SUCCESS	
/HTG/GC_DTLINK1	3908	SUCCESS	
/HTG/GC_DTLINK2	0	NO DATA	
/HTG/GC_ECC_CFG	692	SUCCESS	
/HTG/GC_HEAD	692	SUCCESS	
/HTG/GC_LINKLIKE	646	SUCCESS	
/HTG/GC_MCONFIG	45	SUCCESS	
/HTG/GC_NBR_EXCP	12	SUCCESS	
/HTG/GC_PRVTOREC	2060	SUCCESS	
UTC/CC CIMPLE	400	CHECEFEE	

### **Upload process**

**Tip**: Prior to performing an upload it is recommended that you perform a new download to save off the configuration or at least have one from a recent download just in case it is necessary to use that file for restoration purposes.

- 1. In order to execute an upload, the user must first select the Upload radio button
  - With this action, the screen will update accordingly
- With regards to the Table Update Instructions, use the default setting of 'Delete all recs, then Insert' or update it to use 'Insert new, Modify existing'
- 3. With regards to the Post-Processing Option 'Remove Non-Existent Tables', select it as required
- 4. Click the 'Execute' button to initiate the upload process
- 5. A confirmation message will appear (Fig. 5.23); select 'Upd. Tables' to continue or 'Cancel' to abort the process



- 6. Since the program is attempting to access the respective file on the user's local directory, this window may appear (Fig. 5.24). The user will need to select 'Allow' for the program to continue or otherwise select 'Deny'.
  - Selecting the latter option will cancel the process and the config will not be uploaded
  - This window may not appear if the user has previously selected the 'Remember My Decision' checkbox

SAP GUI Security	Fig.	gure 5.24
The system is trying to access the file		
C:\GoldClient\GoldClientConfig_EST800.txt		
Do you want to grant access to this file?		
□ <u>R</u> emember My Decision		
Allow Deny	Help	

7. Once the program completes processing, one of two output versions will appear on the screen; the version that appears is based on whether the user selected the 'Remove Non-Existent Tables' option since it has its own output

- Both versions of the output show the tablename, the number of records read from the file, and a status (Fig. 5.25 and 5.26)
- If the 'Remove Non-Existent Tables' option was selected, a Post-Processing column will be visible, and content with respect to this program will appear at the end of the output (Fig. 5.26)
- The only status expected to appear in these outputs is 'SUCCESS'; if for some reason a different outcome is encountered, it is recommended that you contact the Qlik team for support

Figure 5.25

### UP ### Load				
912770	3   🐴	🗟 👿 🛛		
Table Name	Rec. Ct.	Status		
/HTG/BDLS	187	SUCCESS		
/HTG/GCSPARMETER	4	SUCCESS		
/HTG/GCSTIMESTMP	17	SUCCESS		
/HTG/GCS_ALTMAP	71	SUCCESS		
/HTG/GCS_CHG_DOC	37	SUCCESS		
/HTG/GCS_TAGS	4	SUCCESS		
/HTG/GCS_TAG_DT	5	SUCCESS		
/HTG/GC_DTLINK1	3908	SUCCESS		
/HTG/GC_ECC_CFG	692	SUCCESS		
/HTG/GC_HEAD	692	SUCCESS		
/HTG/GC_LINKLIKE	646	SUCCESS		
/HTG/GC_MCONFIG	45	SUCCESS		
/HTG/GC_NBR_EXCP	12	SUCCESS		
/HTG/GC_PRVTOREC	2060	SUCCESS		
/HTG/GC_SIMPLE	490	SUCCESS		
/HTG/GC_SLCR_CFG	14	SUCCESS		
/HTG/GC_TABLES1	7342	SUCCESS		
/HTG/GC_TABLINK	11385	SUCCESS		

Figure 5.26

### UP ##;	# Loa	d	
914770	3   🍋	🚯 👿 (	🛓 🖽
Table Name	Rec. Ct.	Status	Post Processing
/HTG/GC_MCONFIG	45	SUCCESS	
/HTG/GC_NBR_EXCP	12	SUCCESS	
/HTG/GC_PRVTOREC	2060	SUCCESS	
/HTG/GC_SIMPLE	490	SUCCESS	
/HTG/GC_SLCR_CFG	14	SUCCESS	
/HTG/GC_TABLES1	7342	SUCCESS	
/HTG/ZTABLEMAP	3291	SUCCESS	
/HTG/ZTABLEMAP_H	100	SUCCESS	
Post Proc.			11/06/2019 Gold Client - Synchronise TABLES1 and TABLINK entries
Post Proc.			
Post Proc.			
Post Proc.			START OF REPORT
Post Proc.			
Post Proc.			FOLLOWING RECORDS WERE DELETED:
Post Proc.			/HTG/GC_TABLINK: GCS - DATA ECHO CONFIG /HTG/GC_TABLES1 /HTG/GLC_CFG_PPU TABLENAME
Post Proc.			
Post Proc.			END OF REPORT
Post Proc.			============

### Intelligent Slice

This utility provides an easy solution for maintaining the Intelligent Slice screen. From here, fields can be added, deleted, activated or deactivated, and even the sequence in which they appear on the screen. Even further, a user description can be defined which would then be displayed on the Intelligent Slice screen instead of SAP's long field label. An entry must be set as 'Active' to become visible on the Intelligent Slice screen (Fig 6.0).

Be sure to select the Update button to save any changes which have been made.

				Figure 6.0
Intelligent Slid	ce Configuration			
Ŭ	J			
3   1 - 2   2	Ŋ <u>an</u> d <b>`</b> a`⊞	🚺   📙 Update		
Data Element	Long Field Label	User Description	Active	Seq. Nbr.
BLART	Document Type		$\checkmark$	1
BSART	Order Type		$\checkmark$	2
BUKRS	Company Code		$\checkmark$	3
EKORG	Purch. Organization		$\checkmark$	10
GJAHR	Fiscal Year		$\checkmark$	4
MATNR	Material		$\checkmark$	5
MONAT	Posting Period			6
SYDATUM	Current Date	Date Range	$\checkmark$	7
VBELN	Sales and Distribution Document Numb			11
VKORG	Sales Organization		$\checkmark$	8
WERKS_D	Plant		$\checkmark$	9

The screen definition in Figure 6.0 controls the appearance of the Intelligent Slice screen (Fig. 6.1).

			Figure 6.1
Intelligent Slice			
() Execute			
Export ID			
Description	R		
Data Selection Criteria			
Document Type		to	<b>=</b>
Order Type		to	<b></b>
Company Code		to	<b></b>
Fiscal Year		to	<b></b>
Material		to	<b>-</b>
Date Range		to	<b>=</b>
Sales Organization		to	<b>=</b>
Plant		to	<b></b>
Purch. Organization		to	<b></b>

Figure 7.0

### Parallel Processing

This utility establishes important constraints for Gold Client exports and imports which utilize background processing. These settings define the maximum number of processes used and on which servers.

The value entered in the 'Max jobs per server at 1 time' field defines the maximum number of processes per server that Gold Client can use at anyone time. The 'Select Servers' section provides the flexibility to choose which servers can be used by Gold Client processing. Using this example (Fig. 7.0), Gold Client would be allowed to use up to 12 background processes since the 'Max' has been defined as 4 and all three servers have been selected.

Parallel Processing Setting	5
Execute	
Current Parallel Configuration	
Select own servers Message Server picks servers	(ACTIVE) (INACTIVE)
Server selection approach	
<ul> <li>Select own servers</li> <li>Message Server picks servers</li> </ul>	
Accelerator Options	
Max jobs per server at 1 time Check job status in Minutes Submit Job Interval (>3 sec )	4 1 5
Worker jobs	
Worker wait (min) before stop	3
Select Servers	
hayes-hp-ux01_EST_02 hayes-hp-ux01_EST_14 hayes-hp-ux01_EST_15	✔HP-UXBig✔HP-UXBig✔HP-UXBig

The 'Select Servers' section also provides informational content regarding each server's operating system and Endianess. This may be critical information as Gold Client exports and imports must use the same Endianess. If, for example, an organization uses a mix of Unix and Linux servers, only one type should be used in both the source and target systems to ensure that data copies will work successfully (Fig. 7.1).

Select Servers         hayes-hp-ux01_EST_02       Image: HP-UX       Big         hayes-hp-ux01_EST_14       Image: HP-UX       Big         hayes-hp-ux01_EST_15       Image: HP-UX       Big				Figure 7.1
hayes-hp-ux01_EST_02Image: HP-UXBighayes-hp-ux01_EST_14Image: HP-UXBighayes-hp-ux01_EST_15Image: HP-UXBig	Select Servers		· · · · · · · · · · · · · · · · · · ·	
hayes-hp-ux01_EST_14✓HP-UXBighayes-hp-ux01_EST_15✓HP-UXBig	hayes-hp-ux01_EST_02	<	HP-UX	Big
hayes-hp-ux01_EST_15	hayes-hp-ux01_EST_14	$\checkmark$	HP-UX	Big
	hayes-hp-ux01_EST_15	$\checkmark$	HP-UX	Big

Alternatively, it is possible to allow the Message Server to choose the servers instead of selecting them manually. This can be achieved by selecting the 'Message Server picks servers' radio button. The screen will update accordingly with this config setting showing as (ACTIVE) and the 'Select Servers' section being hidden since it is no longer relevant (Fig. 7.2).

Figure 7.2

Parallel Processing Set	tings
€ Execute	
Current Parallel Configuration	
Select own servers	(INACTIVE)
Message Server picks servers	(ACTIVE)
Server selection approach	
Select own servers	
Message Server picks servers	
Accelerator Options	
Max jobs per Instance	4
Check job status in Minutes	1
Submit Job Interval (>3 sec )	4
Worker jobs	
Worker wait (min) before stop	5

### Global Scenario Variables

This config area is used for creating static variables that can be used either as part of the Scenario creation or within the Data Echo framework itself.

The primary use case for creating variables is to limit the amount of historical data that is exported. For example, an organization is using the HR module and generates payroll data. A user may want to copy one or more Personnel Records but not copy multiple years of payroll data because it just adds overhead to the copy process and does not provide any meaningful value; instead, it makes more sense to truncate the collection process to be that of only the last 1-2 years (depending on the user's requirements). In order to fulfill this use case, there are two steps that need to be executed: (1) defining the variable and (2) applying the variable within the respective areas of the Data Echo config.

When in change mode, the New Entries selection enables the creation of a new variable definition in three steps:

- Enter the variable name
- Input the Data Element to use (must be an existing Data Element)
- Enter the desired value

Once saved, the As Stored in DB column will show the value as it is stored in the database. Data elements of the same type (i.e. CHAR, DATS, and NUMC) can be used interchangeably, for example, ERDAT can be used for <u>all</u> date fields.

The 'Date Format' column is relevant when a date value is being entered in the 'As Entered' column. This format should default from the user's settings but can be changed here in case the user wants to input date value with a different format.

This image illustrates several examples of variables (Fig. 8.0).

#### Figure 8.0

Change View "Variables for Scenario Sql": Overview								
by New Entries 👔 🖶 🖪 🖡 🖡								
Variables for Scenario Sql								
Variable	Data element	As Entered	As stored in DB	Created By	DateFormat			
COMPANY_CODE	BUKRS	0001	0001	EBYRNE	<b>•</b>			
CONTROLLING_AREA	KOKRS	0001	0001	EBYRNE	•			
CREATE_END_DATE	ERDAT	06302008	20080630	SGEORGE	MM/DD/YYYY 🔻			
CREATE_START_DATE	ERDAT	04012008	20080401	SGEORGE	MM/DD/YYYY 🔻			
CREDIT_CONTROL_AREA	KKBER	0001	0001	EBYRNE	<b>•</b>			
DIVISION	SPART	01	01	EBYRNE	•			
HR_END	ERDAT	01012002	20020101	TOLIVERO	MM/DD/YYYY 🔻			
HR_START	ERDAT	01012000	20000101	TOLIVERO	MM/DD/YYYY 🔻			
PAYROLL_DIRECTORY_E.	ERDAT	123108	20081231	SGEORGE	MM/DD/YYYY 🔻			
PAYROLL_DIRECTORY_I	IPEND	123108	20081231	SGEORGE	MM/DD/YYYY 🔻			
PLANT	WERKS_D	0001	0001	EBYRNE	<b>•</b>			
PURCHASING ORG	EKORG	0001	0001	EBYRNE	•			
SALES_ORG	VKORG	0001	0001	EBYRNE	<b>•</b>			
SHIPPING_POINT	VSTEL	0001	0001	EBYRNE	•			
WAREHOUSE	LGNUM	001	001	EBYRNE	<b>•</b>			
payroll_directory_fpbeg	FPBEG	01012014	20140101	SGEORGE	MM/DD/YYYY 🔻			
payroll_runid_PP	P_EVNUM	3563	3563	SGEORGE	<b>•</b>			

This image illustrates an example of a variable being applied within the Data Echo framework when linking from one Data Type to another Data Type (Fig. 8.1). It is only possible to apply variables when linking two Data Types.

In this example, an export that uses Data Type HR - EMP MAST WITH PAY POSTING will perform a join to table HRPY\_RGDIR but the restriction of FPBEG > = 20140101 will be applied which will help limit the data that is exported (because this is the value assigned to the variable).

							Figure 8.
🖙 System Heb						🔄 Value for field contents in S	QL statement (1)
	۲. JN					Restrictions	
	2 IN						V
Gold Client Data Framework						X X X X X X X X X X X X X X X X X X X	1
	_	_	_		_	Variable	As stored in DE
🗟 Create 👘 Copy 📑 Delete 🍸 Primary Data Type	٦	🖗 Master Data Type	Transaction D	ata Type	📷 Display All	COMPANY_CODE	0001
Data Framework						CONTROLLING_AREA	0001
GCS - APPLICATON SETTINGS		HR - EMP M	AST WITH	PAY PC	DSTING	CREATE START DATE	20080401
GCS - CLIENT CONSTRUCT CONFIG	-	DT Kind	File ID	Primary	Primary Date	CREDIT_CONTROL_AREA	0001
GCS - DATA ECHO CONFIG		Master Data	HR-E	<b>v</b>	AEDTM	DIVISION	01
GCS - EXPORT CONFIG						HR_END	20020101
GCS - HR EVALUATION PATHS			-6.6.	3		HR_START	20000101
GCS - INTELLIGENT SLICE CONFIG		Linkages [ Display M	nde l			PAYROLL_DIRECTORY_ERDA	20081231
• 🔚 GCS - LISTS		Desirient DT	Nuc 1		Transferre	payrol_drectory_tpbeg	20140101
GCS - RFC DESTINATIONS				VBFA FI.	Inactive	PAYROLL_DIRECTORY_IPEND	20081231
GCS - TRANSFORMATION CONFIG			TER (PCL4 - UI)	_	<u>v</u>		0001
• GM - BUDGET DOCUMENT		HR - THIRD PARTY	EVAL DOCS			PURCHASING ORG	0001
GM - FUNDS						SALES ORG	0001
GM - GRANT MASTER				2			
GM - SPLITTING RULES		HR - PAYROLL DIRE	CTORY			17 Entries foun	
		OpParen AND/OR NO	)T Recip. Table	Rec. Eld. (	Operator Prv. Fie	ld Value CIPa	aren
			HRPY RGDIR	PERNR =	= PERNR		
		AND	HRPY RGDIR	FPBEG >	>=	payroll directory fpbeg	

### Structure Differences

Ideally, table structures should be identical when copying data between source and target clients. Gold Client export and import programs have progressively improved to handle these exceptions; however, imports may still fail on an occasional basis because of a structural delta. The import failure should generate a shortdump which can be analyzed to determine the problem table. This utility provides a technical solution for those instances when a failure occurs for a given table.

To make use of this solution, convert the screen to change mode and select the 'New Entries' button. Add the table in the Table Name field and click the Active checkbox to activate the configuration (Fig. 9.0).

It is necessary to define the entry in both the **source and target clients**.

			Figu	ure 9.0
Display View "Tables with	different layo	outs from S	ource to Targ	jet".
🎾 昆 🖪				
Tables with different layouts from Source to	) Target			
Table Name	Active			
MARA		<b>^</b>		
		-		

*Note: If an import failed because of this issue and the Structural Changes table has been updated in the respective clients, a new data export <u>must</u> be generated to make use of this solution.* 

### Select Optimization

This table contains table name and field name values and the disallowed values for each combination (Fig. 10.0). This can be useful when a SQL statement would cause slow performance when there are no values to return. An example of this would be for FI documents by vendor. If the vendor field is not always populated, all FI documents would still be part of the search even though they will never be returned by that query. Disallowing a blank value for the vendor field would stop the performance hit.

		Figure	10.0
Change View "Table/Field Co	ombinations and disallowed	value": Overvie	w
🦻 New Entries 👔 🖥 🕼 🕼			
Table/Field Combinations and disallowed value			
Table Name	Field Name	Value not allowed in SQL	111
BKORM	BELNR	11	-
BSAD	KUNNR	11	$\mathbf{T}$
BSAK	LIFNR	11	
BSAS	HKONT	11	
BSID	KUNNR	11	
BSIK	LIFNR	1 1	
BSIM	MATNR	1 1	
BSIP	LIFNR	11	
BSIS	HKONT	11	

### Memory Optimization

This configuration screen controls how the Gold Client export program collects data into memory and writes it out to the file system (Fig. 11.0).

			Figure 11.0
Change View "Export Memory	Configuration":	Overview	
😚 New Entries 📋 🖶 🖙 🕃 🖡 🚯			
Export Memory Configuration			
Data Type	Coll. per Unit / Wk.	Header Tab Pkg.Sz	
FI - DISPUTE CASE ATTRIBUTES	1.000	20.000	
FI - DUNNING DATA	1.000	20.000	-
FI - DUNNING DATA ACTIVITY LOG	1.000	20.000	
FI - EARMARKED FUNDS	1.000	20.000	
FI - FINANCE DOCS W/ DISP CASES	1.000	20.000	
FI - FINANCE DOCUMENTS	1.000	20.000	
FI - GL ITEMS (FAGLFLEX)	1.000	20.000	
FI - GL SPLIT OPEN ITEMS	1.000	20.000	
FI - LOAN REFERENCE CUMULATION	1.000	20.000	
FI - LOAN REFERENCE DISBURSEMENT	1.000	20.000	
FI - LOANS	1.000	20.000	

- Collections per Unit of Work: A performance control to help limit the amount of memory used by the export process. This parameter controls how many collections are processed before being written to file.
- Header Table Package Size: It may be beneficial to process those exports that target large volumes of data in smaller packages. Like other technical settings, this is designed to reduce the memory consumption on an export. This parameter should only be changed in the event of an export failure due to a large volume export. There may be times to either increase or decrease this value. It is possible that setting this value too low may result in export failure. Please contact Qlik for support issues or questions.

### Transform Order

This table is used to control in which order the data within the listed tables is transformed. The use of this particular utility is exceptional and is typically related to HR data due to the need to both transform it and yet keep it in sync across any number of various data tables.

The input screen requires the entry of a data type; once done, select 'Execute' (Fig. 12.0).

Transformation Table O	rder	Figure 12.0
Data Type	HR - PERSONNEL MASTER	
Execute		

This table only requires the input of multiple tables and the order in which the data is to be transformed (Fig. 12.1).

			Figure 1	2.1
Change View "Transformat	tion Table	e Ordel	r": Overview	
💅 New Entries 📫 🖬 🕼 🛃 🖪				
Data Type HR - PERSONNEL MA	ASTER			
Transformation Table Order				
Table Name	Order			
PA0001	2	•		
PA0002	1	<b>_</b>		

### Application Settings (mconfig)

This table controls a number of miscellaneous configuration settings that are available within Gold Client (Fig 13.0). Those functionality items marked as 'Active' are in use. It's suggested that you contact Qlik for support prior to making any changes to these settings.

Figure 13.0

1iscellaneous Configuration		
Functionality	Active	111
ACCELERATOR	<b>v</b>	-
ALLOW_CLASS_C_TFORM	4	-
ALLOW_CONFLICT_DATA_CHECK_SKIP	$\checkmark$	
ALLOW_CONV_EXIT_COMPLEX	$\checkmark$	
ALLOW_CONV_EXIT_VARIABLE		
ALLOW_DW_EXPORT_NONPRD		
ALLOW_GROUP_BY_TABLES	4	
ALLOW_RR_SUPPORT_PACK_DIFF		
ALLOW_TRANSPORT_OF_COPIES		
CLIENT_SPECIFIC_TABLENAMES	4	
COMPRESSION_NEW_XML		
COMPRESSION_OLD		
CONV_EXPID_FROM_3_TO_4		
DATE_TIME_FILE_NAME_OPTION		
DISABLE_NEWS_WIDGET		
DISABLE_VIEWING_REPORTS		
DONT_VALIDATE_OPSYS		
DONT_WRITE_FILE_BOX	4	
ENFORCE_DATASNAP_MAX_JOBS		
FI_RECONCILIATION_REPORTS	4	
FRAMEWORKLOG	$\checkmark$	
FREE_MEMORY	$\checkmark$	-
GEN_&_ACTV_INTEGRATION_MODEL		Ŧ

In the Miscellaneous Configuration there's an entry named DISABLE\_NEWS\_WIDGET. If this setting <u>is not</u> marked as 'Active' then Qlik, Inc. is able to deliver information such as new releases, updates, and announcements which are delivered in widget form visible on the main Gold Client page (Fig. 13.1). If this setting <u>is</u> marked as 'Active', then the widget is disabled, and support-related details are provided instead (Fig. 13.2).

Gold Client' Solution	ns Q° 🛃	
lient Construct	Data Echo	ATTUNITY SUPPORT
Client Exporter Client Importer Post Process  consitory Replicator  Cobject Alignment System Build Plus	Data Snap     Intelligent Slice     Scenario Segment     Scenario Segment     Import Control     Post Process     Data Transform	Access theHUB B <sup>*</sup> - Tickets - Help Search - Training US HOTLINE +1 877-484-8982 NEWS - New how-to videos - Watch the recorded webinar to ase the new fortune
🔌 Data Wave	Transformation Setup	v8.5.0

Figure 13.2

Data Echo	
	👌 ATTUNITY
🔄 🛛 Data Snap	
Intelligent Slice	ATTUNITY SUPPORT
Scenario Segment	goldclient.support@attunity.com
	Phone: +1 847-543-8982
Export Control	Toll-free US: +1 877-484-8982
Import Control	
Post Process	
Data Transform	
Transformation Setup	
Transformation Audit	

### **Configure Auto Import RFC**

This table is used to administer control over which target clients are available for selection by end-users when using the Import Options feature that is available within the Data Snap and Export Control functions.

Adding an entry to this table means that an end-user can select from this list of destinations so that the import is automatically initiated (via the respective RFC). The entry must be set as 'Active' for it to appear in the selection list; if inactive, it cannot be selected by the end-user (Fig. 14.0).

If the auto-import option is not selected by the user at the time of initiating the export, then the import must be performed manually.

			Figu	ıre 14.0
	Change View "Auto Import RF	C Destinations	": Overview	•
63	🕨 New Entries 📔 📑 🖙 📑 🖪			
	Auto Import RFC Destinations			
	RFC Destination	Active		
	DE3CLNT800		-	
	EC3CLNT800		τ	
	GCTCLNT200	$\checkmark$		

In this sequence, the user selects the Import Options function and must then input or select from the lookup function a valid RFC for the 'Target Destination' field (Fig. 14.1). The list of valid values displayed to the end-user is controlled from the entries stored in this configuration table (Fig. 14.0).

						Figure 14.1
Ехро	ort Control					
🚯 Exect	ute in Foreground	( Schedule Jobs	Tmport Options	XSubset Sync	炉 Data Transform	😫 Export
Export	Erexport Control					×
Create	Trigger Import					
2 Refre	Target Destin	ation				
Select	Parallel Proces	sing On Import		🖻 Logical destination	on (specified in function	call) (3) 1
	Skip Conflicting	) Data Check		Restrictions		
	Destrict Import					<u>v</u>
	Restrict Import			RFC Destination		
	Target System	n ID		GCTCLNT200		
	Target Client J		_			

**Important Note:** the RFC that is used for Import Options functionality must be setup (in t-code SM59) as a named user. The import options functionality <u>will not</u> <u>work</u> if the RFC is set with 'Current User'. An example of this can be seen where the RFC has an actual user assigned and the 'Current User' checkbox is not set (Fig. 14.2).

				Figure 14.2
Administration Technical	Settings / Logon &	Security MDMP &	Unicode Special Op	tions
Trusted System   No	O Yes	Logon Screen		* *
Status of Secure Protocol				
SNC  Inaction	ve O Active			
Authorization for Destination				
Logon				
Language EN Client 300		Current Us	er	
PW Status saved				
				-
4 F		:		< >

### Simulate Export Setup

This utility is used in conjunction with the Simulate Export option that is available within Export Control. Its sole purpose is to create estimates for dependent data objects. The only way to create these estimates is to initiate a data export.

Here's a hypothetical example: if a simulated export of 1000 sales orders is executed and it locates 2000 related billing documents and 3500 related material documents, then the ratio of sales orders to billing docs is 1:2 and for sales orders to material docs is 1:3.5. Now, when the user is in Export Control and has a Scenario for exporting 5000 sales orders it will estimate that your export will include 10,000 billing docs (based on the 1:2 ratio) and 17,500 material docs (based on the 1:3.5 ratio).

In the utility you enter a sample of how much data to review (a range between 1,000 and 10,000 is typical), a date range, and which data types you would like to include in the estimate (Fig. 15.0).

You can execute for all data types or selectively choose date types. Understand that if running for all data types that the export job may run for quite some time, so it is suggested that specific data types be used when possible.

			Figure 15.0
Simulate Export Setup	,		
•			
Data Selection Criteria			
Data Flow Estimator Count			
Date range		to	<b>=</b>
All Date Field DT's	۲		
Select Data Type(s)			

Once initiated, a message will appear (Fig. 15.1). This just informs the user that the record count process has been initiated. The job can be monitored via t-code SM37.



The next message informs the user which Export ID has been generated by the execution of this simulated export (Fig. 15.2). The results can be viewed by using the Export Control function located on the main Gold Client screen.

⊡ Information	Figure 15.2
Created - Export ID [0006] with [1] containers.	
	< 2

The final message informs the users that the simulated export job has been initiated (Fig. 15.3). The job can be monitored via t-code SM37.

C Information	Figure 15.3
Job DFE Generation 20190610 SGEORGE was     successfully submitted.	ר ב
	</td

Figure 16.0

### Maintain User Exits

This table is used to add programs that need to be applied during various times of the copy process. This typically involves some additional processing that is beyond just the copying of data from Source to Target or even data transformation.

It is generally recommended that users work with the Qlik support team when needing to make changes to existing user exits or when new user exits are required. This is to help ensure that this config is defined correctly and to help ensure that the user's requirements are successfully achieved.

The table is comprised of the following elements (Fig. 16.0):

- Table Name: input the relevant table
  - Utility Type: when the user exit is to be applied
    - Available options are After Import, Before Import, During Export, and During Import
- Data Type: input if the user exit needs to apply to a specific Data Type
  - If left blank, the user exit will be applied to each Data Type that contains the relevant table (what is in the 'Table Name' field)
- Report Name: input the program name
  - Active: check if the user exit is active or not
    - If an entry is set in the table as 'Active', and the given table is part of the export then the user exit will be executed automatically

Change View "Maintain User Exits": Overview									
💖 New Entries 🗈 🖶 🖾 🎚 🖡 📳									
Maintain User Exits									
Table Name	Util. Type	Data Type	Report Name	Active					
CDHDR	During Import 🔻		TG/GCS_USEREXIT_CHANGE_DOC	<b>v</b>					
CDPOS	During Import 🔻		/HTG/GCS_USEREXIT_CHANGE_DOC	<b>v</b>					
EORD	Before Import 🔻		/HTG/GLC_UTL_C_18						
LQUA	Before Import 🔻		/HTG/GLC_UTL_C_21	<b>v</b>					
PA0003	Before Import 🔻		/HTG/GLC_UTL_C_15	<b>v</b>					
PCL2	After Import 🔹		/HTG/GLC_UTL_C_07						
STXL	After Import 🔻		/HTG/GLC_UTL_C_10						

# **Utilities**

### Logical System Configuration

During the import of data, Gold Client will change the Logical System name from the Logical System name assigned in the Source to the Logical System name assigned in the Target; an example is visible via t-code SCC4 where the client is defined (Fig. 19.0). Performing this conversion during import replaces the need to run BDLS to convert the Logical System name.

The Qlik team provides this configuration by default but users may freely maintain this table as required to include any tables and fields that need to be converted during import for the various AWSYS or LOGSYS type of fields.

Display View "	Clients": Details
🦻 🔓 🔛	
Client	800 IDES-ALE: Central FI Syst
City	Frankfurt - Deutschland
Logical System	T90CLNT090

Enter the tables to be converted in the Table Name column and in the Field Name column, input the respective field. If the box in the Active column is checked, then the respective table/field will have its Logical System name converted during import; if not checked as Active, then the Logical System name will not be converted (Fig. 19.1).

The Use BDLS Map column can be selected when additional logic is required due to data being replicated to connected systems (CRM, for example). See the next section titled Logical System Mapping for more details.

Figure 19.1

Figure 19.0

Change View "Logical System Fields to update": Overview										
🥎 New Entries [ 🗎 层	, <b>s</b>									
Logical System Fields to	update									
Table Name	Field Name	Active	Use BDLS Map	11						
ACCTHD	AWSYS									
ACEPSOIT	AWSYS	Image: A start of the start		Ŧ						
AMYOTREE	LOGSYS	<b>V</b>								
ANEK	AWSYS	<b>V</b>								
ARIX_BKPF	AWSYS	<b>v</b>								
AUAK	AWSYS	<b>v</b>								
AUFK	LOGSYSTEM	✓								
BCST_BOR	LOGSYS	<b>v</b>								
BDAUDQUEUE	SND_SYSTEM	<b>v</b>								
BDAIIDSTATE	SND SYSTEM									

### Logical System Mapping

Logical System Mapping allows for the conversion of Logical System values in those environments where multiple SAP solutions are utilized and are connected to each other. In the preceding section titled <u>Logical System Configuration</u>, content is shared that describes how the Logical System value stored in the source will be converted to match the value stored in the target; however, in connected systems like CRM, SRM, GTS, EWM, etc. this simple conversion logic will not necessarily lead to positive results. This is because the Logical System value points to the system from which the data was sourced.

For example, there may be data in CRM such as a Business Partner that was initially created in ECC and then replicated to CRM; the Logical System field in the CRM table(s) will therefore contain the ECC Logical System value even though the data is in CRM.

A simple Logical System conversion would not lead to ideal results because it would convert the value to the **CRM target Logical System** and not the **connected ECC target Logical System**. Thus, the import program will interrogate the entries in this table (as required according to the settings defined in the Logical System Configuration table) and use these "mappings" to determine how to convert the Logical System values.

Add new entries to this table according to the organization's requirements and specific Logical System values. The value in the first Logical System column represents the Source value and the second Logical System column represents the target value (what it needs be converted to). The BDLS App column is just informational but helps provide visibility on where each conversion/mapping is used. In this example, the config is defined in a CRM system where the ECC Logical System values need to be converted from ERPCLNT800 to ERPCLNT200 (Fig. 19.2).

			F	igure 1
Change Vie	ew "BDLS	Map": Overview		
🤣 New Entries	n 5. s			
BDLS Map				
Logical System	Logical System	BDLS App	311	
ERPCLNT800	ERPCLNT200	Customer Relationship Manager		
		Enterprise Resource Planning	-	
		Customer Relationship Manager		
		Supplier Relationship Manager		
		Advanced Planning and Optimization		
		Buisness Information Warehouse		
		Human Resources		
		Global Transport System		
		Product Lifecycle Management		

### Activity Log

Cold Cleant Activity Lag Report

All exports, imports, and deletions are logged for reference and monitoring purposes, and so this utility can be used to view those details.

The input screen provides the user the flexibility to query this history in numerous ways (Fig. 20.0):

- Export only, import only, or deletion only, or all of them collectively
  - Additionally, the user can choose to query exports just by the Header data type which is the default setting (Fig. 20.1) or by all data types. See output examples for each to understand the difference; with default setting (Fig. 20.2) and with this setting off (Fig. 20.3). The Header data type is highlighted just for visibility, and it is possible in this case to see the other five data types that were included in the export.
- User Name, Created on, Data Type, Export ID, and Run time ID

Figure 20.0

Gold Client Activity Log Re	eport		
(D)			
Logging Source			
🔘 Export			
<ul> <li>Import</li> </ul>			
🔘 Delete			
<ul> <li>All</li> </ul>			
✓ Show only Header Export DT's			
Logging Characteristics			
User Name		to	
Created on		to	
Data Type		to	
Export ID (relevant 4 Exp)		to	
Run time ID		to	

Figure 20.1

Show only Header Export DT's

											Figure 20.2
Gold Client Activity Log Report											
Exp/Imp	Run Time ID	Container	Data Type	Exp ID	Sc.Num	User	Start Dt.	St. Time	Col. Ct.	Seconds	Background Job Name
E	107420190603174321	1	CA - SERIAL NUM FOR GOODS MVMNT	1074	999	SGEORGE	06/03/2019	11:43:21	25	0	MATDOC TO SN TO EQ TE

#### Figure 20.3

Sold Clent Activity Edg Report											
Exp/Imp	Run Time ID	Container	Data Type	Exp ID	Sc.Num	User	Start Dt.	St. Time	Col. Ct.	Seconds	Background Job Name
E	107420190603174321		LINK - SERIAL NUMBER TO EQUIPMNT	1074		SGEORGE	06/03/2019	11:43:21	0	0	MATDOC TO SN TO EQ TE
E	107420190603174321		CA - EQUIPMENT DATA	1074		SGEORGE	06/03/2019	11:43:21	122	1	MATDOC TO SN TO EQ TE
E	107420190603174321		CA - INSTALLED BASE	1074		SGEORGE	06/03/2019	11:43:21	2	0	MATDOC TO SN TO EQ TE
E	107420190603174321	1	CA - SERIAL NUM FOR GOODS MVMNT	1074	999	SGEORGE	06/03/2019	11:43:21	25	0	MATDOC TO SN TO EQ TE
E	107420190603174321		LINK - OBJECT TO CLASSIFICATION	1074		SGEORGE	06/03/2019	11:43:22	1	0	MATDOC TO SN TO EQ TE
E	107420190603174321		CA - CLASSIFICATION DATA	1074		SGEORGE	06/03/2019	11:43:22	1	1	MATDOC TO SN TO EQ TE

The report's output displays the following information:

- Exp/Imp: Identifies the relevant process with 'E' for export, 'I' for import, or 'D' for deletion
- Run Time ID: Unique value assigned to each process execution
- Container: Container number used in the process
  - Displayed only for exports
- Data Type: Data Type used in the process
- Exp ID: The Export ID used in the process
- Sc.Num: Scenario used in the process
  - Displayed only for exports
- User Name: Who executed the process
- Start Dt: Date on which the process was executed
- St. Time: Time on which the process was executed
- Col. Ct: The record count from the Header table in the Data Type that was processed
- Seconds: Number of seconds for the process to be executed
- Background Job Name: Name of background job used during processing

Here is a sample output (Fig 20.4).

											Figure 20.4	
Gol	Gold Client Activity Log Report											
Gold Clie	ent Activity Log Report											
Exp/I	Run Time ID	Container	r Data Type	Exp ID	Sc.Num	User Name	Start Dt.	St. Time	Col.	Seconds	Background Job Name	
E	112020190610222127	1	SD - SALES DOCUMENTS (T)	1120	999	TOLIVERO	06/10/2019	16:21:34	1	1	SD 11542 GCT	
E	111920190610221347	1	SD - SALES DOCUMENTS (T)	1119	999	TOLIVERO		16:13:55	1	9	SD GCT	
I	107420190610195443		CA - EQUIPMENT DATA	1074		SGEORGE		13:54:45	710	1		
I	107420190610195443		CA - INSTALLED BASE	1074		SGEORGE			70	1		
I	107420190610195443		CA - SERIAL NUM FOR GOODS MVM	1074		SGEORGE		13:54:44	353	1		
D	107420190610195334		CA - SERIAL NUM FOR GOODS MVM	1074		SGEORGE		13:53:37	353	0		
D	107420190610195334		CA - EQUIPMENT DATA	1074		SGEORGE		13:53:35	710	0		
D	107420190610195334		CA - INSTALLED BASE	1074		SGEORGE			70	0		
E	001420190606210014	1	CA - BUSINESS PARTNERS	14	5	GOLDSKH	06/06/2019	15:00:14	115	28		
E	001420190606205949	1	CA - BUSINESS PARTNERS	14	5	GOLDSKH		14:59:49	115	2	GOING FOR SS2	
E	001420190606205225	1	CA - BUSINESS PARTNERS	14	5	GOLDSKH		14:52:26	115	2	GOING FOR SS	
E	001420190606204901	1	CA - BUSINESS PARTNERS	14	5	GOLDSKH		14:49:02	115	8		

### **Configuration Change Log**

This report can be executed to display all changes made to the Client Construct and Data Echo frameworks. The report can be executed using optional filters: User Name, Change Date, and/or Data Type (Fig 21.0).

		Figure 21.0
Configuration Change Log		
•		
Selection Criteria		
User Name	to	
Change Date	to	
Data Type	to	

The execution of this utility's output (Fig. 21.1). Any comments entered by the user at the time of change are displayed in the 'Reason for change' column.

						Figure 21.1
Gold Clie	ent: Config	uration (	Change Log			
	_					
Gold Client: Con	figuration Change	Log				
User Name	Date	Time	Data Type	Config Event	Reason for change	
TOLIVERO	06/10/2019	16:08:49	SD - SALES DOCUMENTS (T)	COPIED DT		*
SGEORGE	06/07/2019	15:36:00	CA - BUSINESS PARTNERS	TABLES		Ψ.
SGEORGE	06/07/2019	15:31:39	CA - BUSINESS PARTNERS	TABLES		
SGEORGE	06/07/2019	15:30:15	CA - BUSINESS PARTNERS	TABLES		
SGEORGE	06/07/2019	15:29:20	CA - BUSINESS PARTNERS	TABLES		
GOLDSKH	06/06/2019	14:45:55	CA - BUSINESS PARTNERS	LINKAGES		
GOLDSKH	06/06/2019	14:43:24	CA - BUSINESS PARTNERS	LINKAGES		
GOLDSKH	06/06/2019	14:43:02	CA - BUSINESS PARTNERS	LINKAGES		
GOLDSKH	06/06/2019	14:41:05	CA - BUSINESS PARTNERS	CONNECTOR		
SGEORGE	06/06/2019	12:08:20	CA - BUSINESS PARTNERS	CONNECTOR		
SGEORGE	06/05/2019	17:02:13	CA - BUSINESS PARTNERS	CONNECTOR		
SGEORGE	06/03/2019	12:34:59	SD - SALES DOCUMENTS	LINKAGES		
SGEORGE	06/03/2019	12:34:27	SD - SALES DOCUMENTS	LINKAGES		

There are various config events that can be displayed:

- CONNECTOR Subset Sync config has been maintained
- COPIED DT A new Data Type has been created via the copy function
- DATASNAP Data Snap config has been maintained
- DELETE DT A Data Type has been deleted
- ECCONFIG Memory parameters have been maintained
- LINKAGES A link from this Data Type has been maintained; this event also occurs with respect to maintaining the linkage details
- NEW DT A new Data Type has been created •
- TABLES A table relation within this Data Type has been maintained; this event also occurs with respect to maintaining the common fields

Figure 22.0

### Configuration Download

This utility allows a user to download the Gold Client configuration to several different formats. The most common use case is for copying the config from a higher-level system like Prod down to lower-level system. This can only be achieved using the 'Flat File' format. Freely download to Excel or XML when useful.

Select the radio button of the desired format, select which parameters should be included, and then select the Execute button to run the utility (Fig 22.0).

Col	nfiguration Download Utility
Ð	
Select	: File Format
۲	Flat File
0	Excel File
0	XML File (only Data Echo Config will export)
. 1.152	
	onal Parameters
4	Export Gold Client Data Echo Config
4	Export Gold Client Client Construct Config
$\checkmark$	Export Gold Client Transformation Rules
<b>V</b>	Export Gold Client Scenarios and Export IDs

The Flat File format will generate export files for each option selected in the additional parameters section (Fig. 22.1). These export files can then be used to import this configuration into another client via the Import Control function.

## **Gold Client Export**

Gold Client Export Report 06/25/2019 13:46:12 Export ID: 0012 Gold Client Config Export 20190625.134557 SGEORGE Export Processing Summary Results
Passport Filename and path /usr/sap/trans/goldclient/g-c-PASS_E0012_GCT_800.20190625.134558
Container Data Type Number of Collections written to file Filename and path
0004 GCS - EXPORT CONFIG 00001060 [/usr/sap/trans/goldclient/g-c-E0012_GCS_EX_C0004_GCT_800.20190625.134610 ]
0001 GCS - DATA ECHO CONFIG 00000657 /usr/sap/trans/goldclient/g-c-E0012_GCS_ID_C0001_GCT_800.20190625.134558
0002 GCS - CLIENT CONSTRUCT CONFIG 00000095 /usr/sap/trans/goldclient/g-c-E0012_GCS_RA_C0002_GCT_800.20190625.134608
0003 GCS - TRANSFORMATION CONFIG 00000017 /usr/sap/trans/goldclient/g-c-E0012_GC_SCR_C0003_GCT_800.20190625.134609

The Excel File format (Fig. 22.2) will dump the contents of the Gold Client configuration tables to a series of Excel Spreadsheets (Fig. 22.3); each spreadsheet will be for a different Gold Client configuration table. When this format is selected, the default file path will be displayed; however, this path can be changed by the user as needed.

		Figure 22.2
Configuration Download Utility		
•		
Code et 51e Francet		
Select File Format		
Flat File		
Street File		
O XML File (only Data Echo Config will export)		
Default File Path	C:\GoldClient\GoldClientConfig.xls	

			Figure 22.3
Name	Date modified	Туре	Size
GoldClientConfig_gcs_bdls_20190610205827	6/10/2019 2:58 PM	Microsoft Excel 97	14 KB
GoldClientConfig_gcs_dtlink1_20190610205827	6/10/2019 2:58 PM	Microsoft Excel 97	862 KB
GoldClientConfig_gcs_ecc_cfg_20190610205827	6/10/2019 2:58 PM	Microsoft Excel 97	14 KB
GoldClientConfig_gcs_head_20190610205827	6/10/2019 2:58 PM	Microsoft Excel 97	56 KB
GoldClientConfig_gcs_impdest_20190610205827	6/10/2019 2:58 PM	Microsoft Excel 97	1 KB
GoldClientConfig_gcs_isconfig_20190610205827	6/10/2019 2:58 PM	Microsoft Excel 97	2 KB
GoldClientConfig_gcs_linklike_20190610205827	6/10/2019 2:58 PM	Microsoft Excel 97	105 KB
GoldClientConfig_gcs_mconfig_20190610205827	6/10/2019 2:58 PM	Microsoft Excel 97	2 KB
GoldClientConfig_gcs_prvtorec_20190610205827	6/10/2019 2:58 PM	Microsoft Excel 97	140 KB
GoldClientConfig_gcs_simple_20190610205827	6/10/2019 2:58 PM	Microsoft Excel 97	64 KB
GoldClientConfig_gcs_syncrfc_20190610205827	6/10/2019 2:58 PM	Microsoft Excel 97	1 KB
GoldClientConfig_gcs_tables_20190610205827	6/10/2019 2:58 PM	Microsoft Excel 97	818 KB
GoldClientConfig_gcs_tablink_20190610205827	6/10/2019 2:58 PM	Microsoft Excel 97	1,353 KB
GoldClientConfig_gcs_userexits_20190610205827	6/10/2019 2:58 PM	Microsoft Excel 97	1 KB
GoldClientConfig_gcs_ztablemap_20190610205827	6/10/2019 2:58 PM	Microsoft Excel 97	308 KB
GoldClientConfig_gcs_ztablemap_h_20190610205	6/10/2019 2:58 PM	Microsoft Excel 97	4 KB

The XML File format (Fig. 22.4) will only copy the Data Echo configuration to an XML format (Fig. 22.5).

÷22.4
22.5
<b< td=""></b<>
÷

## Advance Utilities

### Passport File Utility

This utility is used in conjunction with the Parallel Processing feature. If one or more of the Parallel Processing jobs fails, then some or all of the data files associated with that part of the export would be missing from the passport file. This utility is useful in those instances when it's decided that the data which was exported successfully can be imported into the Target client even though not all of the data was exported successfully and thus some data will be absent in the Target. A passport file can be generated to bundle together all of the data files so that the import process can be initiated.

*Note: this program is relevant to the legacy export engine which existed in Gold Client versions preceding 8.5. With the 8.5 version, the export engine was rewritten for optimization purposes and the typical response to a canceled job would be to use the 'Restart Failed Jobs' utility instead.* 

In this example, jobs 001-005 and 007 finished successfully; however, job 006 canceled (Fig. 23.0). If the decision is made that the data that would have been collected via export job 006 is not needed in the target client, then this utility can be used to generate the necessary Passport file and so that the import can proceed.

Job	Ln	Job CreatedBy	Status
<ul> <li>AU_TOLIE9650109_0002_001</li> <li>AU_TOLIE9650109_0002_002</li> <li>AU_TOLIE9650109_0002_003</li> <li>AU_TOLIE9650109_0002_004</li> <li>AU_TOLIE9650109_0002_005</li> </ul>	aaaaaa	TOLIVERO TOLIVERO TOLIVERO TOLIVERO TOLIVERO	Finished Finished Finished Finished Finished
AU TOLIE9650109 0002 006	Ī	TOLIVERO	Canceled
AU_TOLIE9650109_0002_007	8	TOLIVERO	Finished

The alternative solution to this problem would be to resolve the root cause of the failed job and repeat its execution.

The only data that is required to execute this utility is the Parallel Processing ID (Fig. 23.1) which can be found within any of the successful export job logs. The files associated with this Parallel Processing ID will be retrieved and can be selected for inclusion into the passport file.

Figure 23.0

#### Figure 23.1

Make Passport File	
€	
Parallel Processing	ם

### Activity Log Cleanup

This utility will remove logs older than the number of days specified. This is helpful because it will purge logs that are no longer needed and thus clears space within the file system.

By default, 60 days is populated and the report only mode is selected. You can also choose to cleanup log files by adding specific Data Type(s) to the selection screen (Fig. 24.0).

			Figure 24.0
Gold Client - Log Entries Clean	nup Utility		
•			
Table /HTG/GC_LOG or /HTG/GC_LOG2			
Data Type		to	
Delete entries NNNN days old	60		
✓Report only (no deletion)			

Here is the output when executed with the 'Report only' option (Fig. 24.1). It lists the relevant data type as well as the date and time the log was created.

			Figure 24.1		
Gold Client - Log	Gold Client - Log Entries Cleanup Utility				
Gold Client - Log En	ntries Cleanup Utility				
Would be deleted:	FI - FINANCE DOCUMENTS	01/25/2017	02:56:49		
Would be deleted:	HR - PERSONNEL MASTER	01/25/2017	02:51:05		
Would be deleted:	SD - SALES DOCUMENTS	01/25/2017	02:51:05		
Would be deleted:	LINK - PERNR TO ORG MANGT	01/25/2017	02:51:09		
Would be deleted:	FI - FINANCE DOCUMENTS	01/25/2017	02:51:18		
Would be deleted:	LINK - FI TO OPERATING CONCERN	01/25/2017	02:51:18		
Would be deleted:	LINK - FINANCE DOC TO FAGLFLEXA	01/25/2017	02:51:19		
Would be deleted:	MM - MATERIAL VALUATION	01/25/2017	02:51:19		
Would be deleted:	SD - CUSTOMER MASTER	01/25/2017	02:51:19		
Would be deleted:	SD - DELIVERIES	01/25/2017	02:51:20		
		01/05/0015	00 51 00		

To run the log deletion, remove the checkmark from the 'Report only' option and execute. Here is the output when executed without the 'Report only' option (Fig. 24.2).

Fiq	ure	24.	2

# Gold Client - Log Entries Cleanup Utility

### Gold Client - Log Entries Cleanup Utility

Deleted	:	FI -	FINANCE DOCUMENTS	01/25/2017	02:56:49
Deleted	:	HR -	PERSONNEL MASTER	01/25/2017	02:51:05
Deleted	:	SD -	SALES DOCUMENTS	01/25/2017	02:51:05
Deleted	:	LINK	- PERNR TO ORG MANGT	01/25/2017	02:51:09
Deleted	:	FI -	FINANCE DOCUMENTS	01/25/2017	02:51:18
Deleted	:	LINK	- FI TO OPERATING CONCERN	01/25/2017	02:51:18
Deleted	:	LINK	- FINANCE DOC TO FAGLFLEXA	01/25/2017	02:51:19
Deleted	:	MM -	MATERIAL VALUATION	01/25/2017	02:51:19
Deleted	:	SD -	CUSTOMER MASTER	01/25/2017	02:51:19
Deleted	:	SD -	DELIVERIES	01/25/2017	02:51:20
Deleted		T.TNK	- DET.TUERY TO TRANSE ORDERS	01/25/2017	02.51.20
### Stranded Files Cleanup

This function can be used to report on those Gold Client files that were created from failed exports; additionally, this program can purge those files. This can be useful since the files consume space in the directory; however, files from more recent failed exports could still be restarted and so the Qlik team suggests targeting only those files that are at least 30-days old. Of course, each organization can use their own discretion to determine how old files should be prior to purging them.

The selection screen allows the user the ability to input dates or a date range, and/or a Runtime ID. The 'Show Report' option is set by default so that the program will only display the records without purging. This may be useful in case the files displayed in the output need to be reviewed before purging (Fig. 25.0).

If the 'Show Report' option is deselected on the selection screen and the program is executed, the file purging will occur immediately without the opportunity to cancel the process.

			Figure 25.0
Stranded files Deletion Utility	,		
Execute			
Selection Criteria			
Show Report	$\checkmark$		
File create dates		to	
Runtime ID (Optional)			

Upon execution, this message should appear (Fig. 25.1). This is to help the user recognize that exports could be in-flight and that this could disrupt those activities. **It is best to purge files when export and import processing is minimized or altogether inactive.** 

📴 File (	Deletion Warning	Figure 25.1
0	Warning!! All Export Activities in this directory will be disrupted.	
		V Ok Cancel

Here is an example of the utility's output (Fig. 25.2).

### Figure 25.2

Select	RuntimeId	Export Id	Source System	Source Cli	Date	Date	Filename		
	000720190610233132	7	EST	800	06/10/2019	23:31:32	/usr/sap/trans/goldclient/g-c-STAT_E000720190610233132_EST_800		
	000720190610224119	7	EST	800	06/10/2019	22:41:19	/usr/sap/trans/goldclient/g-c-STAT_E000720190610224119_EST_800		
	000720190610190950	7	EST	800	06/10/2019	19:09:50	/usr/sap/trans/goldclient/g-c-STAT_E000720190610190950_EST_800		
	405120190603231427	4051	EST	800	06/03/2019	23:14:27	/usr/sap/trans/goldclient/g-c-STAT_E405120190603231427_EST_800		
	405020190603103254	4050	EST	800	06/03/2019	10:32:54	/usr/sap/trans/goldclient/g-c-STAT_E405020190603103254_EST_800		

From the output, it is possible for the user to select entries and use the Delete Selected Files button to delete files.

### Figure 25.3

[		ሽ 💽 💽 📅 Delete	Selected Files					
Г	Select	RuntimeId	Export Id	Source System	Source Cli	Date	Date	Filename
		000720190610233132	7	EST	800	06/10/2019	23:31:32	/usr/sap/trans/goldclient/g-c-STAT_E000720190610233132_EST_800
Г		000720190610224119	7	EST	800	06/10/2019	22:41:19	/usr/sap/trans/goldclient/g-c-STAT_E000720190610224119_EST_800
Г		000720190610190950	7	EST	800	06/10/2019	19:09:50	/usr/sap/trans/goldclient/g-c-STAT_E000720190610190950_EST_800
Г		405120190603231427	4051	EST	800	06/03/2019	23:14:27	/usr/sap/trans/goldclient/g-c-STAT_E405120190603231427_EST_800
Г		405020190603103254	4050	EST	800	06/03/2019	10:32:54	/usr/sap/trans/goldclient/g-c-STAT_E405020190603103254_EST_800

### **Export ID Manager**

The primary purpose of the Export ID Manager utility is to locate and, as needed, delete those Export ID records which are no longer required.

The Export IDs can be found using various inputs: Export ID, Export Type, Data Type, and even the last time the Export ID had been executed. Additionally, the user has the options to choose My Export IDs or All Export IDs in lieu of using any inputs (Fig. 26.0).

				Figure 26.0
Export ID Manager				
My Export IDs	All Export IDs			
Selection Criteria				
Export ID		to	<b>=</b>	
Export Type		to	<b></b>	
Data Type		to	<u> </u>	
Date Last Run	<ul> <li>Any date</li> </ul>			
	<ul> <li>None (never used</li> </ul>	or run)		
	<ul> <li>Last run date is 60</li> </ul>	) days or older		
	<ul> <li>Last run date is 90</li> </ul>	) days or older		
	<ul> <li>Last run date is 18</li> </ul>	30 days or older		
	<ul> <li>Last run date is</li> </ul>			
List Export IDs				

Executing this utility generates the output displayed on the Export ID Manager screen. This information consists of Export ID, Export ID description, Activity Type, Owner, Created On, and Changed On (Fig 26.1).

#### Figure 26.1

Exp	port ID Manager					
	3 I T M L M . B . H (	🚺   <u> Telete Flag</u>	gged Expor	t IDs		
Exp ID	Export Description	Activity Type	Owner	Created On	Changed On	Delete
3	8.6 test: 2008-2010	Intelligent Slice	SGEORGE	05/28/2019	05/31/2019	
5		Intelligent Slice	SGEORGE	06/10/2019		
6		Intelligent Slice	SGEORGE	06/10/2019		
10		Intelligent Slice	SGEORGE	06/25/2019		
13	Subset Sync test (CMS)	Scenario Segment	SGEORGE	06/05/2019	06/12/2019	
1032	Client Construct: Direct Export	Client Construct	SGEORGE	05/28/2019		
1033	Client Construct: Direct Export	Client Construct	SGEORGE	05/28/2019		
1034	Client Construct: Direct Export	Client Construct	SGEORGE	05/28/2019		
1035	Client Construct: Direct Export	Client Construct	SGEORGE	05/28/2019		

The checkboxes in the Delete column can be used to select those Export IDs that are no longer needed. After selecting, choose the 'Delete Flagged Export IDs' button located on the toolbar (Fig. 26.2).

The delete action deletes the Export ID(s) but does <u>not</u> delete the Scenarios which are assigned to the Export ID(s). This deletion activity cannot be undone.

_						F	igure 26.2
	Exp	oort ID Manager					
	9.	ð 1 <b>- 7 (1) - 10 - 10 - 10</b> (10 - 10 - 10 - 10 - 10 - 10 - 10 - 10	Delete Flag	gged Expor	t IDs		
I	Exp ID	Export Description	Activity Type	Owner	Created On	Changed On	Delete
	3	8.6 test: 2008-2010	Intelligent Slice	SGEORGE	05/28/2019	05/31/2019	
	5		Intelligent Slice	SGEORGE	06/10/2019		
	6		Intelligent Slice	SGEORGE	06/10/2019		
	10		Intelligent Slice	SGEORGE	06/25/2019		
	13	Subset Sync test (CMS)	Scenario Segment	SGEORGE	06/05/2019	06/12/2019	
	1032	Client Construct: Direct Export	Client Construct	SGEORGE	05/28/2019		
	1033	Client Construct: Direct Export	Client Construct	SGEORGE	05/28/2019		
	1034	Client Construct: Direct Export	Client Construct	SGEORGE	05/28/2019		
	1035	Client Construct: Direct Export	Client Construct	SGEORGE	05/28/2019		

### Scenario Manager

The primary purpose of the Scenario Manager utility is to locate and, as needed, delete those Scenario Segment records which are no longer required. This data can be found using a wide-range of user inputs such as Data Type, Scenario Number, Export ID, or Not used in an Export ID, and even the last time the Scenario Segment had been executed in an export (Fig 27.0).

Perhaps the most important input is the one named 'Show My Scenarios Only'. Deselecting this setting allows the user to report – and possibly delete – Scenario Segments created/owned by other users; however, there is a security activity set specifically for this option. If the user has the authorization, this option can be deselected; however, if the user is not authorized, then this option is suppressed, and it cannot be deselected, and the result is that the user can only see their own data.

			Figure 27.0
Scenario Manager			
🗎 My Scenarios 🛙	) Manage Variables		
Scenario Search			
Selection Filter			
Data Type		to	
Scenario Number		to	<b></b>
□ Not used in an ExportID			
Export ID		to	<b>S</b>
Date Last Run	<ul> <li>Any date</li> </ul>		
	None (never used of	r run)	
	<ul> <li>Last run date is 60 i</li> </ul>	days or older	
	<ul> <li>Last run date is 90 i</li> <li>Last run date is 90 i</li> </ul>	days or older	
	<ul> <li>Last run date is 180</li> </ul>	l days or older	
	<ul> <li>Last run date is</li> </ul>		
	1		
Show My Scenarios Unly			
List Scenarios			

Executing this utility generates the output displayed on the Scenario Report screen. This information consists of Data Type, Scenario Number and Description, Export ID and Description, Container, Scenario Owner, and Date (Fig 27.1). It may be necessary to scroll in order to view the various columns.

					Figure 2	27.1	
Scer	Scenario Report						
3		1	Delete Flagged Scenarios				
Delete	Data Type	Sc.Num	Scenario Description	Exp IC	Export Description		
	CA - BUSINESS PARTNERS	039	0017A4512C901EE9A38D486AB69F000E = /htg/glc_syncdet-run_guid	0000			
	CA - CASE MANAGEMENT	001	8.6 testing: timestamp	0000		-	
	CA - CASE MANAGEMENT	002	8.6 testing: timestamp	0004	8.6 testing: timestamp		
	CA - CHARACTERISTICS (AUSP ONLY)	001	All AUSP records where Class is not equal to '023'	0021	Batch-related data scenarios (op	p	
	CA - EQUIPMENT DATA	003	8.6 test: 2008-2010	0003	8.6 test: 2008-2010		
	CA - OBJECT STATUS	001	Common Master Data objects	0000			
	CA - OBJECT STATUS	002	Master data object statuses	0001	Master data scenarios (optional	)	
	CA - ORDERS MASTER (AUFK)	004	8.6 test: 2008-2010	0003	8.6 test: 2008-2010		
	CA - TEXT	001	Text for SAPScript and Form objects	0001	Master data scenarios (optional	)	
	CA - TEXT	002	Text for (common) Master Data objects	0001	Master data scenarios (optional		
	CA - VENDOR MASTER	005	8.6 test: 2008-2010	0003	8.6 test: 2008-2010		
	CO - COST COLLECTOR ORDERS	001	All Cost Collector Orders	0001	Master data scenarios (optional	)	
	CO - INTERNAL ORDERS	001	All Controlling (CO) orders	0001	Master data scenarios (optional	)	
	FI - FINANCE DOCUMENTS	006	8.6 test: 2008-2010	0003	8.6 test: 2008-2010		
	FI - PAYMENT RUNS	007	8.6 test: 2008-2010	0003	8.6 test: 2008-2010		

The checkboxes in the Delete column can be used to select those Scenarios that are no longer needed. After selecting, choose the 'Delete Flagged Scenarios' button located on the toolbar (Fig. 27.2). This action deletes the Scenario itself and it also deletes it from the associated Export ID, if this relation exists. This deletion activity cannot be undone.

	Figure 27.2					
S	cenario Report					
	9 1 T M C	I) 🖬	Delete Flagged Scenarios			
Del	ete Data Type	Sc.Nun	Scenario Description	Exp ID	Export Description	
	CA - BUSINESS PARTNERS	039	0017A4512C901EE9A38D486AB69F000E = /htg/glc_syncdet-run_guid	0000		
	CA - CASE MANAGEMENT	001	8.6 testing: timestamp	0000		-
	CA - CASE MANAGEMENT	002	8.6 testing: timestamp	0004	8.6 testing: timestamp	
	CA - CHARACTERISTICS (AUSP ONLY)	001	All AUSP records where Class is not equal to '023'	0021	Batch-related data scenarios (o	p
	CA - EQUIPMENT DATA	003	8.6 test: 2008-2010	0003	8.6 test: 2008-2010	
	CA - OBJECT STATUS	001	Common Master Data objects	0000		
	CA - OBJECT STATUS	002	Master data object statuses	0001	Master data scenarios (optional	)
	CA - ORDERS MASTER (AUFK)	004	8.6 test: 2008-2010	0003	8.6 test: 2008-2010	
	CA - TEXT	001	Text for SAPScript and Form objects	0001	Master data scenarios (optional	)
	CA - TEXT	002	Text for (common) Master Data objects	0001	Master data scenarios (optional	
	CA - VENDOR MASTER	005	8.6 test: 2008-2010	0003	8.6 test: 2008-2010	
	CO - COST COLLECTOR ORDERS	001	All Cost Collector Orders	0001	Master data scenarios (optional	
	CO - INTERNAL ORDERS	001	All Controlling (CO) orders	0001	Master data scenarios (optional	)
	FI - FINANCE DOCUMENTS	006	8.6 test: 2008-2010	0003	8.6 test: 2008-2010	
	FI - PAYMENT RUNS	007	8.6 test: 2008-2010	0003	8.6 test: 2008-2010	

### Change Gold Client File Path

The purpose of the Change Gold Client File Path utility is to change the file directory for <u>existing data files</u> in order to match the value in the Target client in those exceptional cases when the file directory is different from between the Source and Target clients.

Let's hypothesize that the file directory in the **Source** client is named: /usr/sap/trans/goldclient/<FILENAME> and therefore the generated files are named like this:

```
/usr/sap/trans/goldclient/g-c-E913_CAADDR_C0001_EI4_800.20121113.132825
```

However, the file directory for the **Target** client is

/usr/sap/trans/goldclient/EI4/<FILENAME> where "EI4" is part of the directory, and so to be able to import this file, it must be renamed like this: /usr/sap/trans/goldclient/EI4/g-c-E913\_CAADDR\_C0001\_EI4\_800.20121113.132825

Upon selecting this utility, this confirmation message appears (Fig. 28.0). There are no user inputs required as all existing files in the Target will be updated.

		Figure 28.0
🖻 Ca	onfirm Step	×
0	T This utility will change the file path in all Gold Client export files	٦
$\bullet$	L to the file path used in this pather. Do you want to continue?	L .
	to the file path used in this system. Do you want to continue?	
	/	
		V OK Cancel

### Export Table Data (CC)

The Export Table Data utility provides the user another method for exporting data; however, this program is limited to copying data from only a single table, and the data can only be segmented on the first key field (not including the MANDT / Client field), and only single values (no ranges) can be used within the selection criteria.

An R3Trans process is used in this program to export data just like the R3Trans method that exists within Client Exporter; however, when using Client Exporter all data within the table is exported, whereas this program allows the user the additional flexibility to export only a segment of the table data.

This program is most useful when there is a need to export a significant volume of data from a single table and where the selection can be segmented by the primary key field.

Enter a table name and then select the 'Selection Criteria' button; in this example, table ZMATERIAL\_IDES is entered (Fig 29.0).

	Figure 29.		
Gold Client - Export Table Dat	ta		
) Selection Criteria 🖓 Export			
Table Name	ZMATERIAL_IDES		
Program uses R3TR Trans technology to export data. Thus, to import data goto Client Importer>R3Trans Method			

On the following screen the first field on whichever table was entered will appear. Enter the data selection criteria as needed and then save the changes (Fig 29.1).

		Figure 29.1
Selection Screen ZMAT	ERIAL_IDES	
Dynamic selections		
Material Master(IDES Demo) Material	HT-1000	

Once the data selections have been entered, return to the main screen and select the 'Export' button (Fig 29.2).

			Figure 29.2
Gold Client -	Export Ta	ble Data	
) Celection Criteria	Export		
Table Name		ZMATERIAL_IDES	

Enter a job name and then the 'Accept' button (Fig 29.3). A message will appear that the job has been submitted. The background job is used only to report when the R3Trans data collection has started and ended. The background job can be monitored via t-code SM37.

 ⊡ SAP		Figure 29.3
Schedule Job		
Job name		
L		
	A Accept 92 C	
	Accept Accept	ancer

Once the export is complete, the import process can only be executed using the Client Importer function and the R3Trans Method. Refer to the <u>Client Construct User</u> <u>Guide</u> for instructions.

### Resend Subset Sync Job

If a Subset Sync export cancels in the connected system, it is possible to restart it using Gold Client's **Resend Subset Sync Job** utility.

Input the following required and optional fields (Fig 30.0):

- Top GUID
- Run GUID
- Ensure that the 'Resend' button is selected
  - There is also an option to perform the 'resend' in foreground

**Note**: The Top GUID and Run GUID values can be found towards the end of the respective export job log (Fig 30.1); copy and paste these values from the log into their respective fields

Click the 'Execute' button to initiate the process. The results of the initiated process can be checked via t-code SM37 in the connected Source system.

	Figure 30.0
Resend Subset Sync Job	
€>	
Top GUID	И
Run GUID	
(TR)ansform (A)udit GUID	
<ul> <li>Resend</li> <li>Execute Resend in Foreground</li> </ul>	
ODelete all /HTG/ Sync tab recs	
Reset Counter Num Range to	2000002
Current # for /HTG/COUNT SNRO	0

											r iyure 30.
*SUBS	SET SY	NC JOB	*	START				*SUBS	ΕТ	SYNC JOE	3*
Gold	Clien	t Subs	et Sync	Job [8.5	5 SUBSET	SYNC	TEST]	submitted	to	RFCDEST	[CR7CLNT800]
s	Source	syste	m		Datatype	e [SD	- SAL	ES DOCUMENT	S]		
w	ill c	onnect	to Syn	c system	Datatype	e [CR	M - SAI	LES HEADER]			
TOP_G	SUID:	0017A4	512C901	EE69C8C87	76F0743CI	B00					
RUN G	SUID:	0017A4	512C901	EE69C8C81	6F0C2481	B00					

Figure 20 1

# System

## **Cross-Client File Names/Paths**

Export files are created and stored in a very similar fashion to the archiving process. This makes use of logical paths and file names controlled through SAP standard transaction code FILE.

The Logical file path required for the Gold Client application is /HTG/GC as highlighted in Figure 31.0.

Figure 31.0

🎾 New Entries 🛅 🛃 🖄			
Dialog Structure			
🔽 🔂 Logical File Path Definiti			
🗀 Assignment of Physi	Create a logical file nath		
🗀 Logical File Name Defini	Lexical file neth	News	
Definition of Variables		Name Minister DEV/to EDD_Long	
Syntax Group Definition		Migration BEV to ERP - Logs	
Assignment of Operating		0 valaivat iuto vatta	
		ArchiveLink path	
		WinGOI Check Tool Installation on PC	-
		Windol Check Tool Default Memory Location	-
		AIRS Workers' Comp. file path (CA)	-
	ARCHIVELINK_CONNECT_CUSTOMIZE_UNIX		-
	ARCHIVELINK_CONNECT_COSTOMIZE_WINDOWS		-
	ARCHIVELINK_DELIMITER	Separator between path and file name	-
	ARCHIVELINK_VIEWER_CUSIUMIZE_WINDUWS		-
	ARCHIVE_APPLICATION	Archiving path for application archiving	-
	ARCHIVE_BCSETS	BC Set Archiving	-
	ARCHIVE_BI_PROTOCOL_PATH	Path for BI log data archiving	
	ARCHIVE_GLOBAL_PATH	Global path for archiving files	
	ARCHIVE_GLOBAL_PATH_WITH_ARCHIVE_LINK		
		Entry 4 of 405	
	E Position	Entry 1 of 125	

# Change View "Logical File Path Definition": Overview

Figure 31.1 ¢ **- -** × Table View Edit Goto Selection Utilities System Help Ø ै। 🗸 📙 । 😋 😧 🖳 🛗 🛗 🖄 🖆 🖧 🏹 🔜 😰 📳 Change View " Assignment of Physical Paths to Logical Path": Details 🎾 New Entries 👔 🚽 🐼 🛃 🛃 Dialog Structure /HTG/GC Logical path 🗢 🗀 Logical File Path Definiti Name Assignment of Physi Logical File Name Defini UNIX Unix compatible Syntax group Definition of Variables /usr/sap/trans/goldclient/<FILENAME> Physical path Syntax Group Definition Assignment of Operating

Here is an example of the Logical to Physical path assignment (Fig. 31.1).

This is the extent of what must be configured manually. The actual logical file names are produced with the creation of Data Types which is an automated process within the Gold Client software (Fig. 31.2).

		Figure 31.2
		<b>_</b>
Table View Edit Goto Sei	ection Utilities System Help	
	] 4 📕   😋 🚱 😫 🗄 🖓   🛱 🎝	🗘 🛠   🔣 🛃   😰 📲
Change View "Logi	cal File Name Definition, Cross	s-Client": Overview
🎾 🕄 New Entries 🗈 🔒		
Dieleg Chusture		
V Clange Structure		
Assignment of Physics		
Logical File Name Defini	Logical file	Name
Definition of Variables	/BEV1/CA_MIGFILE	Migration BEV to ERP - Logs and Mapping
🔁 Syntax Group Definition	/HTG/	GOLD CLIENT:
Assignment of Operatinc	/HTG/1A-ABSENTFIELDRELATIONSTEST	GOLD CLIENT: 1A - ABSENT FIELD RELATIONS
	/HTG/A-ELBTEST	GOLD CLIENT: A - ELB TEST
	/HTG/A-ELBTEST2	GOLD CLIENT: A - ELB TEST 2
	/HTG/A-ELBTEXT	GOLD CLIENT: A - ELB TEXT
	/HTG/A-EXPCONFGTEST	GOLD CLIENT: A - EXP CONFG TEST
	/HTG/A-HTGCONFIG	GOLD CLIENT: A - HTG CONFIG
	/HTG/A-HTGCONFIGCOPY	GOLD CLIENT: A - HTG CONFIG COPY
	/HTG/A-HTGEXPORTS	GOLD CLIENT: A - HTG EXPORTS
	/HTG/A-HTGEXPORTSCOPY	GOLD CLIENT: A - HTG EXPORTS COPY
	/HTG/A-HTGTEST	GOLD CLIENT: A - HTG TEST
	/HTG/A-PA0008	GOLD CLIENT: A - PA0008
	/HTG/A-SALESDOCUMENTS(TEST)	GOLD CLIENT: A - SALES DOCUMENTS (TEST)
	/HTG/A-TCURR	GOLD CLIENT: A - TCURR
	/HTG/A-TEST	GOLD CLIENT: A- TEST
	/HTG/A-TESTFORDELETE	GOLD CLIENT: A - TEST FOR DELETE
	反日	Position Entry 1 of 584
	<u>~</u>	

### Number Range Buffer

This utility is basically a shortcut for SAP standard t-code SM56. It displays number range buffer information including status and value (Fig. 32.0).

After number ranges have been copied between the source and target clients, it is necessary to execute this transaction to refresh the buffers. For more information on how this transaction is used with respect to Gold Client, see the document titled <u>Gold</u> <u>Client 8.6 Number Range User Guide</u>.

Figure 32.0

Number Range Buffer						
🛐 Buffer Times Server Times 🛛 🚔 🐺 🛛 💹 🗮						
Status	Value					
Max. No. of Entries	1.000					
Current No. of Entries	6					
Max. No. of Indexes	3.000					
Current No. of Indexes	6					
Size	340.144					
Buffer Calls	63.634					
Get Calls	63.634					
Server Calls	6.193					
Database Calls	6.193					
Conflicts	0					
Timeouts	0					

### Data Type Change Pointers

Gold Client now has the capability to generate Change Pointers for Data Imports in a Gold Client target system. The following section will walk you through the steps that need to be completed in order to make sure Change Pointers are created in the target client during the data import process for Data Echo and Client Construct within Gold Client.

 In the target system, ensure the following application setting is active (ZGOLD → Configuration → Application Settings (mconfig)): GENERATE\_CHANGE\_POINTERS

YOU MAY WANT TO ADD THIS APPLICATION SETTING (MCONFIG) ENTRY TO YOUR SOURCE SYSTEM AS WELL, SO THAT IF THE GOLD CLIENT CONFIGURATION IS PULLED OVER TO A TARGET SYSTEM, THIS ENTRY WILL REMAIN ACTIVE IN YOUR TARGET. ACTIVATING THIS SETTING IN YOUR SOURCE SYSTEM WILL UTILIZE THE SAME STEPS AS ABOVE

Display View "Miscellaneous	Configuration	": Overview
🧚 🗈 🖪		
Miscellaneous Configuration		
Functionality	Active	
FI_RECONCILIATION_REPORTS	<ul><li>✓</li></ul>	-
FRAMEWORKLOG	<b>v</b>	<b>*</b>
FREE_MEMORY	4	
GENERATE_CHANGE_POINTERS	<b>v</b>	
GEN_&_ACTV_INTEGRATION_MODEL		

 Gold Client utilizes table **TBD62** in your SAP system to generate Change Pointers in the target system. We will need to utilize this table to find/target tables and message types from our Gold Client Configuration (FELDNAME = KEY) that need to be generated in the target system. Additionally, Change Pointers need to be active within transaction **BD50** to generate Change Pointers – if these are not active in this transaction, then no Change Pointers will be generated

These are the only types of Change Pointers the tool will generate for, where FLDNAME = KEY in table tbd62.

 Open this table and scroll through the list to find the TABLES + MESSAGE TYPES you are wanting to generate Change Pointers for – we need to capture the MESTYP field for the entries in TBD62 to add to the Gold Client Configuration

Ľ	ata Bro	wser: Table Tl	BD62 Select Entries 200		
64		🖪 🖪 🚱 🚺 Che	ck Table		
Tak	ole:	TBD62	E Fixed Columnat	E Tigt Width 0250	
	sprayed	rielus. 5 01	5 Fixed Coldmins.		
	MANDANT	CDOBJCL	MESTYP	TABNAME	FLDNAME
	800	ADDECCE	SEMAGE	ADR10	KEY
h	800	ADRESSE	ADRMAS	ADR11	KEY
h	800	ADRESSE	ADRMAS	ADR12	KEY
In	800	ADRESSE	ADRMAS	ADR13	KEY
h	800	ADRESSE	ADRMAS	ADR14	KEY
h	800	ADRESSE	ADRMAS	ADR15	KEY
In	800	ADRESSE	ADRMAS	ADR16	KEY
In	800	ADRESSE	ADRMAS	ADR2	KEY
In	800	ADRESSE	ADRMAS	ADR3	KEY
Ī	800	ADRESSE	ADRMAS	ADR4	KEY
	800	ADRESSE	ADRMAS	ADR5	KEY
Ī	800	ADRESSE	ADRMAS	ADR6	KEY
	800	ADRESSE	ADRMAS	ADR7	KEY
In	800	ADRESSE	ADRMAS	ADR8	KEY
	800	ADRESSE	ADRMAS	ADR9	KEY
Ī	800	ADRESSE	ADRMAS	ADRC	KEY
	800	ADRESSE	ADRMAS	ADRCT	KEY
Ī	800	ADRESSE	ADRMAS	ADRT	KEY
	800	ADRESSE	FRE LOC ADDRESS	ADR12	KEY
	800	ADRESSE	FRE LOC ADDRESS	ADR2	KEY
	800	ADRESSE	FRE LOC ADDRESS	ADR3	KEY
	800	ADRESSE	FRE LOC ADDRESS	ADR6	KEY
	800	ADRESSE	FRE LOC ADDRESS	ADRC	KEY
	800	ADRESSE2	ADR2MAS	ADCP	KEY
	800	ADRESSE2	ADR2MAS	ADR10	KEY
	800	ADRESSE2	ADR2MAS	ADR11	KEY
	800	ADRESSE2	ADR2MAS	ADR12	KEY
	800	ADRESSE2	ADR2MAS	ADR13	KEY
	800	ADRESSE2	ADR2MAS	ADR14	KEY
	800	ADRESSE2	ADR2MAS	ADR15	KEY
	800	ADRESSE2	ADR2MAS	ADR16	KEY
	800	ADRESSE2	ADR2MAS	ADR2	KEY
	800	ADRESSE2	ADR2MAS	ADR3	KEY
	800	ADRESSE2	ADR2MAS	ADR4	KEY
	800	ADRESSE2	ADR2MAS	ADR5	KEY
	800	ADRESSE2	ADR2MAS	ADR6	KEY

- 4. Once the tables + message type have been targeted, we need to maintain the Gold Client Data Type + Message Type in Datatype Change Pointers within the Configuration Menu of Gold Client (ZGOLD → Configuration → System (folder) → Datatype Change Pointers); this needs to be completed in the target system; (table for these entries are /HTG/GC\_MSGTYP)
- Note, we are able to generate Change Pointers for both the Data Echo and Client Construct side of the tool



5. Within the Data Type Change Pointers screen, you will need to enter the Data Type you wish to use, as well as the Message Type (note, you can use the same Data Type for multiple Message Types). You can use Data Types from both the Data Echo side of the tool as well as Client Construct You will then need to mark these lines as Active, if you wish to generate Change Pointers for the combination that has been entered (as seen below)

aintain data type to message types for cha	ange pointers			
Data Type	Message Type		Active	
CA - CENTRAL ADDRESS MANAGE	ADR2MAS		$\checkmark$	
CA - CENTRAL ADDRESS MANAGE	ADR3MAS		4	
CA - CENTRAL ADDRESS MANAGE	ADRMAS			
CA - GL ACCOUNTS	GLCORE		<b>v</b>	
CA - GL ACCOUNTS	GLMAST	Data Echo Data Tvr	<b>V</b>	
CA - GL ACCOUNTS	GLRED1			
CA - VENDOR MASTER	CREMAS		<b>v</b>	
G/L ACCTS COST & PROFIT CEN	GLCORE		<	
G/L ACCTS COST & PROFIT CEN	GLMAST	Client Construct Data	Types 🚽	
MM - MATERIAL MASTER	ARTMAS		<b>v</b>	
MM - MATERIAL MASTER	MATCOR		4	
MM - MATERIAL MASTER	MATMAS		<b>v</b>	
SD - CUSTOMER MASTER	DEBMAS		4	
SD - CUSTOMER MASTER	DEBMAS_CFS		4	

L	Data Browser: Table TBD62 Select Entries 6							
양 역 🚊 🐺 🕃 🕀 🚹 Check Table								
Table: TBD62 Displayed Fields: 5 of 5 Fixed Columns: <mark>5</mark> ] List Width 0250								
	MANDANT	CDOBJCL	MESTYP	TABNAME	FLDNAME			
	200 200 200 200 200 200	SACH SACH SACH SACH SACH SACH	GLCORE GLCORE GLMAST GLMAST GLMAST	SKA1 SKAT SKB1 SKAT SKB1	KEY KEY KEY KEY KEY			

- 6. Once the Application Setting has been set as active and the Data Type Change Pointers screen has been maintained, when you import data with Gold Client in to a target system, and the tables within the Data Type contain the tables from the Message Type, Change Pointers will be generated in **BDCP2**
- 7. In BDCP2, the following information will be entered while the Change Pointers are generating:
  - a. MESTYPE comes from what is configured in the Gold Client Configuration Area
  - b. CPIDENT Next available Change Pointer Number
  - c. PROCESS left as blank, so the change pointers can be sent to the connected system
  - d. TABNAME Table that was imported from the corresponding data type
  - e. TABKEY Key fields of the table to generate the Change Pointers
  - f. FLDNAME will always be KEY, as this is the only type of Change Pointers, we are current targeting
  - g. CRETIME and ACTTIME time which the data was imported into the SAP system with Gold Client
  - h. USRNAME Name of the user who is doing the importing with Gold Client
  - i. CDCHGID Type of change to the data; in this case, it only works during the import side of things, so we would only expect an I in this field

# **New Utilities**

### **Restart Failed Jobs**

Execute this utility when an export or import job has canceled for some reason and needs to be completed. The program does not start the process completely over but instead it attempts to complete whatever work remains.

To restart a process, input the following (Fig. 33.0):

- a Run Time ID value
  - $\circ$  this value can be found within the export or import job located near the top of the log (Fig. 33.1)
- select the appropriate processing option: Export or Import
  - If the Export option is chosen, select the appropriate type: Client Construct or Data Echo
  - If the Import option is chosen, the screen will change accordingly, including making visible the option of running the import using Parallel Processing (Fig. 33.2)
- additional processing options

	Figure 33.0
Reset the Dataflow Status to Initial	
( Execute	
Run Time ID	
Processing Options	
Export	
OImport	
Export Type	
Client Construct	
OData Echo	
Additional processing options	
Option to ignore validity chk	

Figure 33.1

Job log	Time	Message text uncoded
0.6 (1.0 (0.01.0	10 50 01	
06/12/2019	12:50:31	Job started
06/12/2019	12:50:31	Step 001 started (program /HTG/GCS_ECC_EXP_P_00, variant &000000
06/12/2019	12:50:31	*** START EXPORT************************************
06/12/2019	12:50:32	==> Export ID: 0013
06/12/2019	12:50:32	==> Runtime ID: 001320190612185032
06/12/2019	12:50:32	==> Number of Containers: 1
06/12/2019	12:50:32	==> Maximum Worker Jobs Allowed: 8
06/12/2019	12:50:32	==> STATUS Filename: g-c-STAT_E001320190612185032_GCT_800

Figure 33.2

Reset the Dataflow Status to Initial
Recute
Run Time ID
Processing Options
<ul><li>○ Export</li><li>○ Import</li></ul>
Import Options
Parallel Processing
Additional processing options
Option to ignore validity chk

The program will likely respond with a sequence of messages that will vary based upon the user's inputs. The first is just informational and provides the user some understanding as to the root cause (Fig. 33.3).

🔄 Information	Figure 33.3
Export not complete due to stranded temp files found in /HTG/GCSFLOWPROG.	ר ב

The next message provides the user the name of the background job that was submitted (Fig. 33.4). The job can be monitored using transaction code SM37.



### Table Cleanup Utility

This utility is used to purge entries from the Gold Client tables listed below.

When an export is executed, these tables will be populated while processing but if the export completes successfully, then the records in these tables (for the given export) are automatically deleted; however, for exports which are <u>not</u> successful, the records are left within the tables. As such, executing this program will remove these records.

/HTG/GCSWRKRTABL /HTG/GCSEXPFILES /HTG/GCS\_GETWORK /HTG/GCSFILETODO /HTG/GCSFILEPROG /HTG/GCSFLOWTODO /HTG/GCS\_DERIVET /HTG/GCS\_DERIVEX /HTG/GLC\_TRA\_H /HTG/GLC\_SYNCDET /HTG/GLC\_SYNCHD

This program contains no input screen so selecting it prompts the user with the question about proceeding or not (Fig. 34.0). If 'Yes' is selected, the program will immediately initiate the purging process in the background. While the process is running, a message should appear at the bottom of the screen (Fig. 34.1).



Deletion in Progress for table : /htg/gcsexpfiles

When the process is completed the screen will show how many records were deleted per table. (Fig. 34.2).

Figure 34.2

Clean up Utilit	iy
Clean up Utilitiy	
Table Name	No. of records deleted
/HTG/GCSWRKRTABL	79
/HTG/GCSEXPFILES	30.421
/HTG/GCS_GETWORK	1.601
/HTG/GCSFILETODO	60.221
/HTG/GCSFILEPROG	0
/HTG/GCSFLOWTODO	19.457
/HTG/GCSFLOWPROG	1.145
/HTG/GCS_DERIVET	12
/HTG/GCS_DERIVEX	0
/HTG/GLC_TRA_H	134.374
/HTG/GLC_SYNCDET	514.637
/HTG/GLC SYNCHD	100

## **Global Parameter Maintenance**

This utility can be used to maintain Gold Client's global level parameters. These settings are provided to the customer with recommended defaults in place and changes to the settings would ideally be provided by the Qlik support team on an as-needed basis (Fig. 35.0).

	Figure 35.0					
Change View "Table to maintain Global level parameters": Overview						
🦻 New Entries 👔 🖥 🕼 🚯 🚯						
Table to maintain Global level parameters						
Object	Value					
FILE_TABLENAME_LENGTH	16					
SPLIT_FILE_RECORD_LIMIT	500000					
SUBSET_SYNC_SYNCDET_DELETE_CHUNK	50000					
SUBSET_SYNC_SYNCDET_PCKG_SIZE	50000					

### SQL Trace Comparison

The typical use case for this program would be when a user has copied data from the source to the target and has found data to be missing. The next natural step is to adjust the Data Echo framework so that the missing data is included in future copies but, perhaps the user is unsure of what changes to deploy because they do not know where the missing data is stored. Perhaps the best way to locate this information is to run a SQL trace in the source client (where the data is good) and then compare the trace results to the target client to identify the deltas. The user can input the respective trace details in this utility to perform a comparison between the source and target clients (Fig. 36.0).

Please note that to perform the comparison an RFC is required that allows the source client to communicate with the target client. If a relevant RFC does not exist, your Basis team will need to first create one.

The user can also limit the number of trace records to compare by adjusting the 'Max Records' field; in most cases 5,000 should be more than sufficient for most trace comparisons.

			Figure 36.0
SQL Trace Comparison			
•			
Trace Period			
Date		То	
Time	00:00:00 . 0	00 То	00:00:00 . 999
Max Records	5.000		
RFC Destination			

SQL traces can be executed and collected via standard SAP t-code ST05. To collect a trace, it is recommended that you open two SAPGUI sessions. In one session, first activate the SQL trace, and then in the other session run the relevant t-code that displays the relevant data; when finished, return to the ST05 session and deactivate the trace, and finally display the trace (Fig. 36.1). **Note**: the default setting should be trace type 'SQL Trace' but ensure that it is selected; no other trace types are required.

					Figure 36.						
ST05 Performance Trace											
Activate Trace	Activate Trace with Filter	Deactivate Tr	ace	Display Trace	Display Trace Directory						
Select Trace Typ	e		Cor	nfigure Trace							
SQL Trace			St	ack Trace							
Buffer Trace Enqueue Trace RFC Trace			On ⊙off								
						HTTP Trace			Progress Display On		
						APC trace					
AMC Trace				Off							

After the trace has been generated, display the filter conditions for it (by selecting 'Display Trace' on the ST05 screen) and make note of the date and time details (Fig. 36.2).

			Figure 36.2					
ST05 Filter Conditions for Trace Records								
Trace Types								
✓ SQL Trace	BUF Trace		Enqueue Trace					
RFC Trace	HTTP Trace							
APC Trace	AMC Trace							
Trace Period	Trace Period							
Date	06/27/2019	то	06/27/2019					
Time	19:04:41 . 000	То	19:05:19 . 999					

Copy/paste these date and time details into the SQL Trace Comparison screen. Input an RFC destination, and then execute the program (Fig. 36.3).

		-
Figure	36	.3
		-

SQL Trace Comparison							
Trace Period							
Date	06/27/2019		То				
Time	19:04:41 .	000	то	19:05:19 .	999		
Max Records	5.000						
RFC Destination							

Here is an output example from the execution of this program (Fig. 36.4). The area highlighted in yellow shows the delta that was found where table CE1IDEA finds four records in the source client but zero records in the target client. The area highlighted in orange shows the details that can be used to query the table that is causing the delta. In this example, table CE1IDEA can be queried using the logic where VRGAR = 'F' and RBELN = '0090005220' and COPA\_AWTYP = 'VBRK'. Having this information in hand, the user can hopefully adjust the Gold Client config accordingly in order for this data to be included in subsequent exports.

				Figure 36.4
SQL Trace Comparis	son			
SQL Trace Comparison				1
DAte TIME 06/27/2019 22:46:44	TABLE NAME CE1IDEA	REC CNT(S)RECCNT(T) 4 0	SELECT	
SELECT * FROM "CE1IDEA" 06/27/2019 22:46:49 SELECT /* Buffer Loadin	WHERE "MANDT"='200' AND " T023T g */ * FROM "T023T" WHERE	VRGAR"='F' AND "RBELN"='009000 663 7.263 "MANDT"='200' ORDER BY "T023T'	)5220' AND "COPA_AWT" "."MANDT","T023T"."S	YP"='VBRK' AND ("COPA_AW PRAS","T023T"."MATKL"

Freely reach out to the Qlik support team if assistance with missing data is required. Sharing any trace comparison outputs with Qlik would provide useful insight in order for the team to help resolve the issue. This utility can be used to quickly update Gold Client's memory parameters. These parameters are typically maintained individually via the Memory Optimization utility, but this utility streamlines the maintenance process when changes need to be applied to all data types. This program's primary use case is for Gold Client customers who are upgrading from a pre-8.5 version to 8.5 or later, but it can also be used at other times when relevant. The key here is understanding that this program's execution will affect <u>all</u> data types.

The user must select either the 'Fixed value' or 'Multiply value' processing option where the fixed option is set by default. Qlik's best practice recommendation is to use fixed values and set 'Collections' as 1,000 and 'Package Size' as 20,000 (Fig. 37.0); however, these values are not set by default and so rely on user input.

If the multiply option is chosen, the screen will refresh accordingly (Fig. 37.1).

Memory optimization upgrade utility			
•			
Processing Option			
● Fixed value			
OMultiply Value			
Parameters			
Collections per Unit of Work	1000		
Header Table Package Size	20000		

Figure 37.1

Figure 37.0

Memory optimization upgrade utility		
Des assaina Ontian		
Processing Option		
○Fixed value		
Multiply Value		
Parameters		
Mult. factor for Collections		
Mult. factor for Package Size		

Based on the chosen processing option, input the relevant parameters and execute the program. The message below should appear.

Collections and package size values are modified

To check if the memory parameters were updated, go to the Configuration menu and select the Memory Optimization utility (Fig. 37.2). The values in this table should be displayed according to the user's inputs (Fig. 37.3).

Figure	37 2
Iguic	37.2



Figure 37.3

Display View "Export Memory Configuration": Overview						
🍄 🖪 🖪 🕄						
Expo	Export Memory Configuration					
Data Type Coll. per Unit / Wk. Header Tab Pkg.Sz						
AE	3 - AGENCY BUSINESS DOC FLOW	1.000	20.000			
AB	3 - AGENCY BUSINESS DOCUMENTS	1.000	20.000			
AB	- AGENCY DOCUMENT CONDITIONS	1.000	20.000			
AB	B - REMUNERATION LISTS	1.000	20.000			
AB	B - SETTLEMENT CONDITIONS	1.000	20.000			
AB	B - SETTLEMENT DOC FLOW	1.000	20.000			
AB	3 - SETTLEMENT DOCUMENTS	1.000	20.000			
CA	A - APPLICATION LOG INDX TABLES	1.000	20.000			
CA	A - APPROPRIATION REQ VARIANTS	1.000	20.000			
CA	- ASSET MASTER	1.000	20.000			

### **Compression Exception by Table**

This utility can be used to maintain compression settings. The Gold Client export program contains default compression logic but on occasion tables are found that require the use of a different compression types and so this table can be used to manage those exceptions.

Typically, Gold Client users will not know when this table needs to be populated and instead would be directed here by the Qlik support team.

Populating the table is straight forward in that the table requiring the exceptional compression is entered in the 'Table Name' column and the compression type is selected from the available list in the 'ComprMd' column (Fig. 38.0).

		Figure 38.0
New Entries: Overview of Ad	lded Entries	
<sup>6</sup> ≫ ₽ ₽ ₽ ₽		
Maintenance View for table /HTG/COMPR_EXCP		
Table Name	ComprMd	
	No compression	-
	No compression	T _
	New compression	
	Old compression	
	_	
	No compression "	·
	No compression	-

### Export progress report

This report provides insight to the user to help them understand the progress of an in-flight export. Although the Export Progress Report can be used as a monitoring tool, be advised that the best overall monitoring tools are t-code SM37 or the Export Dashboard located within Export Control.

The user can display the data still to be exported ('In Progress' tab) as well as the data already exported ('Complete' tab). This report also provides the job log for the given export. This is a collective log so that even if the export was initiated as a parallel export, the logging details from <u>all</u> jobs will be displayed here (Fig. 39.0). If the export is complete, the details on the 'In Progress' and 'Complete' tabs will be empty; however, the 'Job Log' details will be present as long as the jobs have not been purged from the system.

Export Progress Report		
Ð		
Runtime ID		
In Progress Complete Job Log		

The only input required by the user is the Runtime ID; this detail is most easily located in the following places: at the very start of the parent's job log (Fig. 39.1), or within the name of the WORKER jobs (Fig. 39.2).

		Figure 39.1
Job log	Time	Message text uncoded
06/26/2019	16:55:51	Job started
06/26/2019	16:55:51	Step 001 started (program /HTG/GCS_ECC_EXP_P_00, variant &000000000130, user ID SGEORGE)
06/26/2019	16:55:51	*** START EXPORT************************************
06/26/2019	16:55:52	==> Export ID: 0003
06/26/2019	16:55:52	==> Runtime ID: 000320190626225552
06/26/2019	16:55:52	==> Number of Containers: 5
06/26/2019	16:55:52	==> Maximum Worker Jobs Allowed: 7
06/26/2019	16:55:52	==> STATUS Filename: g-c-STAT E000320190626225552 GCT 800
06/26/2019	16:55:52	==> PASSPORT Filename: g-c-PASS_E000320190626225552_GCT_800

JobName				
BP, MAT	DOC, MAI	L, CUST	, SD (	ORDER
WORKER_	00032019	0626225	552_00	01
WORKER_	00032019	0626225	552_00	)2
WORKER_	00032019	0626225	552_00	)3
WORKER	00032019	0626225	552 00	)4
WORKER	00032019	0626225	552 00	)5
WORKER	00032019	0626225	552 00	06

Figure 39.2

Figure 39.0

Once a Runtime ID has been entered, select the various tabs to see the relevant content (Fig. 39.3).

A user typically wants insight to try and understand how much longer the export will run and so the 'In Progress' tab is the most useful, but having this information is not all that meaningful without understanding how the export process works. When an export runs, it first interrogates the Data Echo configuration to identify all of the relevant data type links, and then once it has obtained this information, it then exports all of the data relevant to these data types. This is the reason the 'In Progress' tab includes in the 'WSID' column the value of either LINK or FILE. A LINK value indicates that the linkages for the given data type are being discovered, and a FILE value indicates that the data for that data type is being collected and written to file. Ultimately, all data types will complete both processes (except those data types which do not have links so they will only perform the FILE step) and the total Record Count will reach zero indicating that the export is complete. The larger the record counts and the more LINK entries there are, the longer the export is going to take to complete. Select the refresh button to update the report details.

			Figure 39.3
Export Progress Report			
Ð			
Runtime ID 000320190626225552			
In Progress Complete Job Log			
In Progress Complete Sob Log			
Q 17 m to 7, 2,%, (	- <b>0.</b>		
Data Type	WSID <sub>2</sub>	Record Count <sup>2</sup>	File Size
		54.683	4.096.672
FI - FINANCE DOCUMENTS	LINK	819	157.248
LINK - MATERIAL TO FORECASTING	LINK	9.164	458.200
LINK - MATERIALS TO ROUTINGS	LINK	142	14.484
MM - APPROVED MFG PARTS LISTS	LINK	8	416
MM - MATERIAL VALUATION	LINK	2.110	248.980
MM - PIR	LINK	292	23.944
SD - CUSTOMER MASTER	LINK	11.147	512.762
MM - MATERIAL DOCUMENTS	LINK	1.847	99.738
CA - BILL OF MATERIALS	FILE	333	14.652
CA - BUSINESS PARTNERS	FILE	18.384	1.507.488
CA - CENTRAL ADDRESS MANAGEMENT	FILE	609	36.540
CA - ENGINEERING CHANGE MGMT	FILE	79	9.480
CA - EQUIPMENT DATA	FILE	20	3.160
CA - FOREIGN TRADE (EXP/IMP)	FILE	1	26
CA - SERIAL NUM FOR GOODS MVMNT	FILE	6	240
CA - TEXT	FILE	827	150.514
CA - TEXT 2	FILE	36	6.552
CO - CO KEY SUBNUMBERS	FILE	51	2.754
CO - LINE ITEMS	FILE	823	74.070
FI - GL ITEMS (FAGLFLEX)	FILE	3.276	327.600

If useful, select the 'Complete' tab to see what data types have finished writing to file (Fig. 39.4). Practically speaking, this is probably useful only if the user is interested in seeing how much data has been exported so far.

		Figure 39.4
Export Progress Report		
Ð		
Runtime ID 000320190626225552		
In Progress Complete Job Log		
Data Type	Σ Record Count	Σ File Size
	• 22.998	<b>2.328.000</b>
CA - BILL OF MATERIALS	11.257	456.000
CA - CENTRAL ADDR MGMT - ADRT	2	24.000
CA - CHARACTERISTICS	768	144.000
CA - CONDITIONS	377	48.000
CA - EQUIPMENT DATA	456	264.000
CA - FOREIGN TRADE (EXP/IMP)	3	72.000
CA - SERIAL NUM FOR SALES ORDERS	10	72.000
CA - TEXT	2.334	432.000
CA - VENDOR EVALUATION CRITERION	18	24.000
CA - VENDOR EVALUATIONS	6	24.000
CA - VENDOR MASTER	540	264.000
CO - CO KEY SUBNUMBERS	68	48.000
CO - LINE ITEMS	1.938	144.000
CO - PA (CE4IDEA)	673	48.000
CO - PA (CE4IDEA_ACCT)	674	48.000
FI - MATERIAL LEDGER	1.358	192.000
FI - PCA (GLIDXA)	2.516	24.000

If useful, select the 'Job Log' tab to see the collective logging details (Fig. 39.5). The first log displayed will be the parent job, but it is possible to scroll down through the log to eventually locate the logging for the various WORKER jobs.

Export Progress	Re	port
-----------------	----	------

### **9**

### Runtime ID 000320190626225552

In Progress	Complete Jo	b Log

	o ' 🗗 ' 🖩	🗄 I 🚺 I 🚺 I						
Background Job Name	Job log entry	Job log entry	End date	End time	J	Msg	М	Message text uncoded
BP, MATDOC, MATL, CUST, SD ORDER	16:55:51	06/26/2019			R	516	S	Job started
BP, MATDOC, MATL, CUST, SD ORDER	16:55:51	06/26/2019			R	550	S	Step 001 started (program /HTG/GCS_ECC_EXP_F -
BP, MATDOC, MATL, CUST, SD ORDER	16:55:51	06/26/2019			R		S	*** START EXPORT ************************************
BP, MATDOC, MATL, CUST, SD ORDER	16:55:52	06/26/2019			R	40	S	==> Export ID: 0003
BP, MATDOC, MATL, CUST, SD ORDER	16:55:52	06/26/2019			R	41	S	==> Runtime ID: 000320190626225552
BP, MATDOC, MATL, CUST, SD ORDER	16:55:52	06/26/2019			R	1	S	==> Number of Containers: 5
BP, MATDOC, MATL, CUST, SD ORDER	16:55:52	06/26/2019			R	1	S	==> Maximum Worker Jobs Allowed: 7
BP, MATDOC, MATL, CUST, SD ORDER	16:55:52	06/26/2019			R	42	S	==> STATUS Filename: g-c-STAT_E00032019062
BP, MATDOC, MATL, CUST, SD ORDER	16:55:52	06/26/2019			R	42	S	==> PASSPORT Filename: g-c-PASS_E000320190
BP, MATDOC, MATL, CUST, SD ORDER	16:55:52	06/26/2019			R		S	==> TRANSFORMATION Rules:
BP, MATDOC, MATL, CUST, SD ORDER	16:55:52	06/26/2019			R	70	S	====> CA - BUSINESS PARTNERS ~> BP04
BP, MATDOC, MATL, CUST, SD ORDER	16:55:52	06/26/2019			R	70	S	====> CA - CENTRAL ADDRESS MANAGEMENT
BP, MATDOC, MATL, CUST, SD ORDER	16:55:52	06/26/2019			R	70	S	====> CA - VENDOR MASTER ~> VM01
BP, MATDOC, MATL, CUST, SD ORDER	16:55:52	06/26/2019			R	70	S	====> SD - CUSTOMER MASTER ~> CM01
BP, MATDOC, MATL, CUST, SD ORDER	16:55:52	06/26/2019			R	70	S	====> SD - SALES DOCUMENTS ~> CM01
BP, MATDOC, MATL, CUST, SD ORDER	16:55:53	06/26/2019			R		S	
BP, MATDOC, MATL, CUST, SD ORDER	16:55:53	06/26/2019			R		S	*** COLLECT HEADER DATA KEYS**********
BP, MATDOC, MATL, CUST, SD ORDER	16:55:53	06/26/2019			R	45	S	~~~> CONTAINER [0002] DATATYPE {CA - BUS
BP, MATDOC, MATL, CUST, SD ORDER	16:55:54	06/26/2019			R	46	S	<< 18384 >> records found for header table [BU]
BP. MATDOC, MATL. CUST. SD ORDER	16:56:01	06/26/2019			R	903	I	Job WORKER 000320190626225552 001 was suc

### Maintain Timestamp types

This utility can be used to maintain date and timestamp conversion settings when necessary. It is most relevant with respect to the Intelligent Slice function where users typically input a date range and then those date values are saved as selection criteria within Gold Client Scenarios. If the conversion is not completed successfully then the values stored in the selection criteria may be incorrect or invalid and cause less than ideal results when running the export for this Scenario.

Be aware that this issue is not common when using date-related fields which are assigned a DATS data type such as these examples (Fig. 40.0).

				Figure 40.0
BLART	BLART	CHAR	2	O Document type
BLDAT	BLDAT	DATS	8	<sup>0</sup> Document Date in Document
BUDAT	BUDAT	DATS	8	<sup>0</sup> Posting Date in the Document
MONAT	MONAT	NUMC	2	<sup>0</sup> Fiscal period
CPUDT	CPUDT	DATS	8	<sup>0</sup> Day On Which Accounting Document Was Entered
CIDITION (		TTY A	6	OT CEL

Typically, Gold Client users will not know when this table should be populated and instead would be directed here by the Qlik support team.

Populating the table is reasonably simple in that the relevant domain, data type element, or conversion exit is entered in the first column and the conversion type is selected from the available list in the second column. It is also possible to activate or inactivate these entries as needed (Fig. 40.1).

Change View "Tracks 1	imestamp Conversion E	Exits and Do	omains": Ov	rerview
🦻 New Entries 👔 🗟 🗐 💽 🖪	. 🗗			
Tracks Timestamp Conversion Exits a	nd Domains			
Domain/Dtel/ConvExit	TimSt/DM		Active	
ADTST	Timestamp	-	$\checkmark$	-
CLMTS	Timestamp	-	$\checkmark$	-
DATS	Date	-	$\checkmark$	33
DATUM	Date	-	$\checkmark$	
GHOTS	Timestamp	-	$\checkmark$	
RETZS	Timestamp		$\checkmark$	
TCTST	Date		$\checkmark$	
TIMES	Other		$\checkmark$	
TSABI			$\checkmark$	
TSHME	Timestamp	•	$\checkmark$	
TSTAM	Timestamp	-	$\checkmark$	
TSTLC	Timestamp	-	$\checkmark$	
TSTMP	Timestamp	-	$\checkmark$	
TSTPS	Timestamp	-	$\checkmark$	
TSTRM	Timestamp	-	$\checkmark$	
TZNTSTMPS	Timestamp	-	$\checkmark$	
TZTMP	Timestamp	-	<b>V</b>	

### Export Dashboard

This program is appropriately named as it is a user's dashboard for managing exports. This dashboard is primarily designed for an advanced user, perhaps someone on the team who is tasked with performing data refreshes and/or copying large data volumes and thus requires advanced monitoring and administration functions because of these responsibilities. The idea is that this dashboard replaces and centralizes various SAP t-codes that could be used for monitoring purposes, primarily SM37 (Background Job monitor), SM50 (Work Process monitor for single instance), and SM66 (Work Process monitor for all instances).

The dashboard provides monitoring capabilities by displaying the following important elements: Job Name, Status, Start Date and Time, Duration, and other useful details like whether the export included data transformation and/or Subset Sync functionality. It is possible to display other more advanced details as well when useful.

The dashboard defaults the Start Date ('today' minus 30-days) and User Name; however, the user may change them as required (Fig. 41.0); if changed, select the Refresh button to update the output. The user may also wish to input one or more specific job names in order to filter the contents in the dashboard.

			Figure 41.0
Export Dashboard			
Refresh			
Start Date	05/27/2019	to	
User Name	SGEORGE	to	
Job Name		to	

Here is an example of the default content provided in the dashboard (Fig. 41.1). Most of the columns displayed are self-explanatory; however, here are a few details for those that may not be.

- Status: red = canceled export, yellow = active export, green = completed export
- Job Log: to display the log for a specific job, click 'Job Log'
  - This screen capture provides an example of the ALV-style job log that should be displayed (Fig. 41.2)
  - Tip: when placing a cursor on it, Job Log should become underlined indicating that it can be selected
- **Tform**: if a light bulb is displayed, data transformation was active for one or more Data Types for the export
- **Subset**: if a light bulb is displayed, Subset Sync was active for one or more Data Types for the export

						F	igure 41.1
JobName	Status	Start Date	Start Time	Duration	Job Log	Tform	Subset
• 0100006843-6846		06/27/2019	13:59:00	00:00:07	Job Log		
• = 8.6 TEST: 2008-2010: 1800 ORDERS	00	06/27/2019	18:34:41	00:03:56	Job Log	30	
• 🛄 🗌 8.6 TEST: 2008-2010: HR & ORDERS	040	06/28/2019	10:40:17	00:00:00	Job Log	:5	
AU_SGEOE001006220190625_0001_001		06/25/2019	13:21:02	00:00:03	Job Log	:5	
AU_SGEOE001006220190625_0001_011		06/25/2019	13:21:32	00:00:11	Job Log	:5	
AU_SGEOE001006220190625_0001_016		06/25/2019	13:21:47	00:01:40	Job Log	:5	
AU_SGEOE001006220190625_0001_021		06/25/2019	13:23:02	00:00:24	Job Log	30	
AU_SGEOE001006220190625_0001_022		06/25/2019	13:23:05	00:00:30	Job Log	30	
Image: Provide the second s	00	06/26/2019	16:55:51	00:04:39	Job Log	:	
• 🦰 🗌 JAN 2012	00	06/26/2019	11:02:27	00:00:28	Job Log	:	
• 📃 🗌 SUBSET SYNC TEST (CMS): 3 DT'S	00	06/12/2019	12:50:31	22:08:51	Job Log	30	:0

#### Figure 41.2

Export	Dashboa	rd		
3 🛓	<b>=mm</b>	<b>7</b> .   <b>2</b> .   9	E	
Job log	Job log entry	Message ID	Msg.no. Msg.ty	/p Message text uncoded
10:40:17	06/28/2019	00	516 S	Job started
10:40:17	06/28/2019	00	550 S	Step 001 started (program /HTG/GCS_ECC_EXP_P_00, variant &000000000132, user ID SGEORGE)
10:40:17	06/28/2019	/HTG/GCS	S	*** START EXPORT ************************************
10:40:18	06/28/2019	/HTG/GCS	40 S	==> Export ID: 0003
10:40:18	06/28/2019	/HTG/GCS	41 S	==> Runtime ID: 000320190628164018
10:40:18	06/28/2019	/HTG/GCS	1 S	==> Number of Containers: 2
10:40:18	06/28/2019	/HTG/GCS	1 S	==> Maximum Worker Jobs Allowed: 7
10:40:18	06/28/2019	/HTG/GCS	42 S	==> STATUS Filename: g-c-STAT_E000320190628164018_GCT_800
10:40:18	06/28/2019	/HTG/GCS	42 S	==> PASSPORT Filename: g-c-PASS_E000320190628164018_GCT_800
10:40:18	06/28/2019	/HTG/GCS	S	==> TRANSFORMATION Rules:
10:40:18	06/28/2019	/HTG/GCS	70 S	====> CA - CENTRAL ADDRESS MANAGEMENT ~> CM01
10:40:18	06/28/2019	/HTG/GCS	70 S	====> CA - VENDOR MASTER ~> VM01
10:40:18	06/28/2019	/HTG/GCS	70 S	====> SD - CUSTOMER MASTER ~> CM01
10:40:18	06/28/2019	/HTG/GCS	70 S	====> SD - SALES DOCUMENTS ~> CM01
10:40:18	06/28/2019	/HTG/GCS	S	
10:40:18	06/28/2019	/HTG/GCS	S	*** COLLECT HEADER DATA KEYS************************************
10:40:18	06/28/2019	/HTG/GCS	45 S	~~~> CONTAINER [0004] DATATYPE {CA - ORDERS MASTER (AUFK)] SCENARIO [004]
10:40:20	06/28/2019	/HTG/GCS	46 S	<< 844 >> records found for header table [AUFK]
10:40:20	06/28/2019	/HTG/GCS	45 S	~~~> CONTAINER [0008] DATATYPE {HR - EMP MAST WITH PAY POSTING] SCENARIO [008]
10:40:21	06/28/2019	/HTG/GCS	46 S	<< 1901 >> records found for header table [PA0003]
10.40.21	06/20/2010	UTC/CCC	C	

The dashboard also consists of these functions: Advanced Details, Job Variant Details, Export Progress, and Restart Failed Jobs (Fig. 41.3); see below for more details on each. **Note**: Advanced Details can be selected without selecting a specific job; however, the other functions require that a job be selected first. If not, the system will respond with the message of "Select one Job Name".



- Advanced Details provides additional details for an export (Fig. 41.4)
  - **Current Table**: from which table an export is actively working
  - **Server**: the server being used by an active export
  - **Export GUID**: the unique ID assigned to each export
  - **Data Type**: the last data type that was exported
  - **LINK/FILE**: in what stage an active export is working (LINK is displayed when the export is identifying the various dependent data

Figure 41.5

relations, and FILE is displayed when the export is collecting data and writing it to file)

- **Job Variant Details** displays the same content as if the user was in t-code SM37, selected an export job, and displayed the variant details (Fig. 41.5)
- **Export Progress** can be used to display details for an in-flight export; reference the section in this user guide named <u>Export progress report</u> for more details on utilizing this function
- **Restart Failed Jobs** can be used to restart an export that resulted in a canceled status; reference the section in this user guide named <u>Restart Failed</u> <u>Jobs</u> for more details on utilizing this function

						Fig	gure 41.4
JobName	Tf	Subset	Current Table	Server	Export GUID	Datatype	LINK/FILE
0100006843-6846					186720190627195902		
8.6 TEST: 2008-2010: 1800 ORDERS	:5				000320190628003442	SD - SALES DOCUMENTS	
8.6 TEST: 2008-2010: HR & ORDERS	:5				000320190628164018	HR - EMP MAST WITH PAY POSTING	
AU_SGEOE001006220190625_0001_001	:5				ASSIGN_BASE_WRONG_		
AU_SGEOE001006220190625_0001_011	:5				ASSIGN_BASE_WRONG_		
AU_SGEOE001006220190625_0001_016	8 <mark>0</mark> 8				ASSIGN_BASE_WRONG_		
AU_SGEOE001006220190625_0001_021	8 <mark>8</mark> 8				ASSIGN_BASE_WRONG_		
AU_SGEOE001006220190625_0001_022	8 <mark>0</mark> 8				ASSIGN_BASE_WRONG_		
BP, MATDOC, MATL, CUST, SD ORDER	8 <mark>0</mark> 8				000320190626225552	MM - BATCH WHERE-USED LIST	
JAN 2012	:5				001720190626170228	FI - FINANCE DOCUMENTS	
SUBSET SYNC TEST (CMS): 3 DT'S	:5	35			001320190612185032	A - VBAK	

Job Variant Details									
(CON). (CON)					1				
		INT	12	- 19 🖆 🔁 - 🖽 🖬 🚹					
Selection	Туре	INCL/EXCL	Option	Selection value	Value				
PGUIDJOB	Ρ			005056BA93C61ED9A68A98FBCE2E9951					
PPLELL	Ρ			Х					
P_EXPID	Ρ			0003					
P_FILE	Ρ			/usr/sap/trans/goldclient/					
P_TOPID	Ρ			NO CONNECTOR					
S_CNTNR	S	Ι	EQ	0002	0000				
S_CNTNR	S	I	EQ	0009	0000				
S_CNTNR	S	Ι	EQ	0010	0000				
S_CNTNR	S	I	EQ	0017	0000				
S_CNTNR	S	Ι	EQ	0018	0000				

In addition to the Configuration menu, this function can also be accessed via the Export Control screen by selecting the Export Dashboard button (Fig. 41.6).


Figure 42.0

## Tablename Mapping

This utility can be used to maintain Gold Client parameters in those unique instances when the table name between the source system and target system are not identical (Fig. 42.0). This solution originated with the need to copy data in EWM (Extended Warehouse Management) systems where some tables have a client value incorporated into their names. An example of this is table /1DF/FDR### where ### represents the respective client number.

The utility might be a solution outside of EWM systems, but it is advised that customers to do so with the Qlik support team's guidance so as to achieve the desired result.

				-			
New Entries: Overview of Added Entries							
<sup>™</sup> == == == == == == == == == == == == ==							
M	Mapping table for swapping target table names						
	Source Table Name	Target Table Name	EWM Active	Active			

To deploy a solution specifically for EWM systems, input into the 'Source Table Name' column the full table name or it is also acceptable to input a <u>table name prefix</u>. It is not necessary to input a value in the 'Target Table Name' column. Tick both the 'EWM Active' and 'Active' checkboxes. It is necessary to maintain these settings in the <u>Target client</u>.

These settings will force the import to substitute the client number for the last three characters for those table prefixes entered in this table. It will perform the conversion only if the last three characters are numeric.

A sample table entry that would convert the clients for EWM doc flow tables (Fig. 42.1).

			Figure 42.1	
New Entries: Overview of Added Entries				
<sup>6</sup> ≱ ₽ ₽ ₽ ₽				
Mapping table for swapping target to	able names			
Source Table Name	Target Table Name	EWM Active	Active	
/1DF/		4	✓	

# Conversion

Some data objects are stored in the database with a client value attached. If the client value in the source and targets are different, this data may not display successfully even though the data has been successfully copied to the target. To resolve these various issues, Gold Client has conversion-related utilities that can be used to target each of the areas where these issues reside. The conversion programs that exist currently involve data stored in theses tables: CDHDR and CDPOS (Change docs), STXH and STXL (Text), and ADRV (Address where-used).

This suite of conversion utilities has been moved out of the Configuration menu and is located on the main Gold Client screen under the function named **Post Process** (Fig. 43.0 and 43.1).

	Figure 43.0
Gold Client' Solution	Y 🔗 🔂
Client Construct	Data Echo
Client Exporter	Data Snap
Client Importer	🖆 Intelligent Slice
Post Process	Scenario Segment
Repository Replicator	Export Control
	Import Control
Cobject Alignment	Post Process
System Build Plus	

Post Import Utilities (Optional)		
Utility		
Finance	_	
<ul> <li>Enversion</li> </ul>		
<ul> <li>Configuration</li> </ul>		
• 🐼 Maintain Change Doc Userexit Config		
• 🎲 Update Change Document Client		
<ul> <li>W Utility to Update Client Value</li> </ul>		
• 🎲 Update Person Where-Used Addr Client		
🔹 🦃 Number Range Utility		

Figure 43.1

### Update Change Document Client

After data has been imported, the client number in the change document tables (**CDHDR** and **CDPOS**) may need to be updated from the old client number (source) to the new client number (target). Executing this program will perform that conversion.

The user is required to input the old client number and one or more Change Doc objects (the value stored in CDHDR.OBJECTID).

If useful, the program can be executed first in report mode (the default setting) to identify the number of relevant records found. Select the 'Update table entries' radio button to perform the actual conversion. Freely increase the default 'Max records to process' parameter when required (Fig. 43.2).

Update Change Docum	ent Client
( Execute	
Update parameters	
Old client	
New client	800
Object identifying criteria	
Change doc. object	
Processing options	
<ul> <li>Report on expected ct. only</li> </ul>	
Oupdate table entries	
Max records to process	9.999

A sample output that displays after having executed the program (Fig. 43.3).

Figure 43.3

Update Change Document Client		
Update Change Document Client		
CDHDR Records meeting selection criteria: CDPOS Records meeting selection criteria:	126 383	

#### Utility to Update Client Value

After data has been imported, the client number in the text tables (**STXH**, **STXL**, and **STXB**) may need to be updated from the old client number (source) to the new client number (target). Executing this program will perform that conversion.

The user is required to input the old client number, one or more Text objects (the value stored in STXH.TDOBJECT), and one or more Text IDs (the value stored in STXH.TDID). **Note**: inputting an asterisk (\*) is an acceptable value in the Object and ID fields.

If useful, the program can be executed first in report mode (the default setting) to identify the number of relevant records found. Select the 'Update Table Entries' radio button to perform the actual conversion. Freely increase the default 'Max records to process' parameter when required (Fig. 43.4).

		Figure 43.4
Client Text Object Updater		
<b>(</b>		
Update Parameters		
Old Client	<b>Y</b>	
New Client	800	
Text Identifying Criteria		
Text Object	<b>Y</b>	
Text ID	Y	
Processing Options		
Expected Count Report		
OUpdate Table Entries		
Max Records To Process	9.999	

A sample output that displays after having executed the program (Fig. 43.5).

		riguit
Client Text Object Updater		
Client Text Object Updater		
STXH Records meeting selection criteria: STXL Records meeting selection criteria: STXB Records meeting selection criteria:	2.939 2.939 0	

Figure 43.5

## **Update Person Where-Used Addr Client**

After data has been imported, the client number in address table **ADRV** may need to be updated from the old client number (source) to the new client number (target). Executing this program will perform that conversion.

The user is required to input the old client number, one or more Application table names (the value stored in ADRV.APPL\_TABLE), and one or more Application field names (the value stored in ADRV.APPL FIELD). Note: inputting an asterisk (\*) is an acceptable value in the Application table name and Application field name fields.

If useful, the program can be executed first in report mode (the default setting) to identify the number of relevant records found. Select the 'Update Table Entries' radio button to perform the actual conversion. Freely increase the default 'Max records to process' parameter when required (Fig. 43.6).

		Fig	ure 43.6
Client Person Where-Used A	ddress Updater		
₽			
Update parameters			
Old Client	ĭ		
New Client	800		
Object identifying criteria for table ADRVP			
Appl. table logical name	<b>Y</b>		
Appl. table logical field name	ĭ		
Processing options			
<ul> <li>Expected Count Report</li> </ul>			
OUpdate Table Entries			
Max Records To Process	9.999		

A sample output that displays after having executed the program (Fig. 43.7).

	Figure	e 43.7
Client Person Where-Used Address Updater		
Client Person Where-Used Address Updater		
ADRVP Records meeting selection criteria:	14.550	

----

## Maintain Change Doc Userexit Config

This program is another way of converting client values that are stored in the Change Document (CDHDR and CDPOS) tables but can be thought of as a 2<sup>nd</sup>-generation and more mature solution. It leverages Gold Client's "user exit" functionality so that the client conversion is performed automatically during the data import process.

The scope of the conversion is determined by the values stored within this configuration table which resides in the Post Process menu (Fig. 43.8).

Figure 43.8

Post Import Utilities (Optional)
Utility
• 🛅 Finance
<ul> <li>Conversion</li> </ul>
Configuration
🚱 Maintain Change Doc Userexit Config
• 🎲 Update Change Document Client
・ 🐼 Utility to Update Client Value
• 🚱 Update Person Where-Used Addr Client

The user can freely maintain in this table whatever Change Doc objects require client conversion with respect to the data in their system (Fig. 43.9).

- The 'Change doc. object' column represents the values stored in CDHDR.OBJECTID / CDPOS.OBJECTID
- Selecting the checkbox in the 'OBJECTID field Active' column informs Gold Client to perform the client conversion for values stored in **CDHDR.OBJECTID** and **CDPOS.OBJECTID**
- Selecting the checkbox in the 'TABKEY field Active' column informs Gold Client to perform the client conversion for values stored in **CDPOS.TABKEY**

Figuro	12	٥
riguie	43.	Э

Change View "Maintenance View": Overview					
🦻 New Entries 👔 🖶 📭 💽					
Maintenance View					
Change doc. object	OBJECTID field Active	TABKEY field Active			
/PLMB/RPR_RPR					
/PLMI/GSS_R2B	<b>V</b>				
AENNR	4				
BANK	4	<b>v</b>			
BELEG	<ul> <li>✓</li> </ul>	<b>v</b>			
BELEGD	4	4			
BELEGM	4	4			
BELEGMASS	4	4			
BELEGR	4	4			
BELEGV	4	4			
BKKENTC	4				
IBAN	4	4			
ORDER	4	4			

For the values in this table to be effective, the Change Doc user exits must be active. This config area can be reached by going to the main Gold Client screen and then selecting the Configuration menu, and then on the following screen by selecting Maintain User Exits.

These respective user exits need to exist in this table and be set as 'Active' for this solution to work. Note that there is entry for CDHDR and another for CDPOS so they can be used indepedently when required (Fig. 43.9).

			Figu	ure 43.9	
Change View "Maintain User Exits": Overview					
🦻 New Entries 🗈 🖶 🛱 🖪 🖪					
Maintain User Exits					
Table Name	Util. Type	Data Type	Report Name	Active	
CDHDR	During Import	<b>r</b>	/HTG/GCS_USEREXIT_CHANGE_DOC	<b>V</b>	
CDPOS	During Import •	r	/HTG/GCS_USEREXIT_CHANGE_DOC	<b>v</b>	

Once the Change Doc configuration table has been populated accordingly, and the user exits configured, this client-conversion activity will occur automatically during the import process.

# Support Information

Qlik Analytics (ISR) Ltd. can be contacted either by telephone or via email. Any support related issue regarding problems with or use of the Gold Client software and process can be reported for resolution.

If our offices are closed, or staff is unable to directly respond to a support request, we will respond within 24 hours of the initial call. Problems related to the export or import processing may require code enhancements. If a code enhancement or fix is required, resolution time may vary.

As per the maintenance agreement, any repairs or enhancements to the Gold Client software will immediately be deployed to all customers up-to-date with their maintenance contract. It is the choice of the customer as to if and when such enhancements are implemented. In addition, customers may request a planning session with Qlik to review changes in the software and how the changes might impact their environment.

We can also be contacted to discuss application or feasibility of using the Gold Client process to resolve a current challenge the project team faces. When this is required, a planning session can be scheduled in advance to ensure proper participation by both Qlik and the client.

Corporate Offices:

QLIK TECHNOLOGIES INC. 211 South Gulph Road Suite 500 King of Prussia, PA 19406 United States

Website:

<u>https://www.qlik.com/us/products/qlik-gold-client</u> Contact:

goldclient.support@qlik.com

1-877-484-8982 (Toll Free in the USA)